

Bluetooth[®] Low Energy Protocol Stack

API Reference Manual: GLP

Renesas MCU

Target Device

RL78/G1D

All information contained in these materials, including products and product specifications, represents information on the product at the time of publication and is subject to change by Renesas Electronics Corp. without notice. Please review the latest information published by Renesas Electronics Corp. through various means, including the Renesas Electronics Corp. website (<http://www.renesas.com>).

Notice

1. Descriptions of circuits, software and other related information in this document are provided only to illustrate the operation of semiconductor products and application examples. You are fully responsible for the incorporation of these circuits, software, and information in the design of your equipment. Renesas Electronics assumes no responsibility for any losses incurred by you or third parties arising from the use of these circuits, software, or information.
2. Renesas Electronics has used reasonable care in preparing the information included in this document, but Renesas Electronics does not warrant that such information is error free. Renesas Electronics assumes no liability whatsoever for any damages incurred by you resulting from errors in or omissions from the information included herein.
3. Renesas Electronics does not assume any liability for infringement of patents, copyrights, or other intellectual property rights of third parties by or arising from the use of Renesas Electronics products or technical information described in this document. No license, express, implied or otherwise, is granted hereby under any patents, copyrights or other intellectual property rights of Renesas Electronics or others.
4. You should not alter, modify, copy, or otherwise misappropriate any Renesas Electronics product, whether in whole or in part. Renesas Electronics assumes no responsibility for any losses incurred by you or third parties arising from such alteration, modification, copy or otherwise misappropriation of Renesas Electronics product.
5. Renesas Electronics products are classified according to the following two quality grades: "Standard" and "High Quality". The recommended applications for each Renesas Electronics product depends on the product's quality grade, as indicated below.
"Standard": Computers; office equipment; communications equipment; test and measurement equipment; audio and visual equipment; home electronic appliances; machine tools; personal electronic equipment; and industrial robots etc.
"High Quality": Transportation equipment (automobiles, trains, ships, etc.); traffic control systems; anti-disaster systems; anti-crime systems; and safety equipment etc.

Renesas Electronics products are neither intended nor authorized for use in products or systems that may pose a direct threat to human life or bodily injury (artificial life support devices or systems, surgical implantations etc.), or may cause serious property damages (nuclear reactor control systems, military equipment etc.). You must check the quality grade of each Renesas Electronics product before using it in a particular application. You may not use any Renesas Electronics product for any application for which it is not intended. Renesas Electronics shall not be in any way liable for any damages or losses incurred by you or third parties arising from the use of any Renesas Electronics product for which the product is not intended by Renesas Electronics.
6. You should use the Renesas Electronics products described in this document within the range specified by Renesas Electronics, especially with respect to the maximum rating, operating supply voltage range, movement power voltage range, heat radiation characteristics, installation and other product characteristics. Renesas Electronics shall have no liability for malfunctions or damages arising out of the use of Renesas Electronics products beyond such specified ranges.
7. Although Renesas Electronics endeavors to improve the quality and reliability of its products, semiconductor products have specific characteristics such as the occurrence of failure at a certain rate and malfunctions under certain use conditions. Further, Renesas Electronics products are not subject to radiation resistance design. Please be sure to implement safety measures to guard them against the possibility of physical injury, and injury or damage caused by fire in the event of the failure of a Renesas Electronics product, such as safety design for hardware and software including but not limited to redundancy, fire control and malfunction prevention, appropriate treatment for aging degradation or any other appropriate measures. Because the evaluation of microcomputer software alone is very difficult, please evaluate the safety of the final products or systems manufactured by you.
8. Please contact a Renesas Electronics sales office for details as to environmental matters such as the environmental compatibility of each Renesas Electronics product. Please use Renesas Electronics products in compliance with all applicable laws and regulations that regulate the inclusion or use of controlled substances, including without limitation, the EU RoHS Directive. Renesas Electronics assumes no liability for damages or losses occurring as a result of your noncompliance with applicable laws and regulations.
9. Renesas Electronics products and technology may not be used for or incorporated into any products or systems whose manufacture, use, or sale is prohibited under any applicable domestic or foreign laws or regulations. You should not use Renesas Electronics products or technology described in this document for any purpose relating to military applications or use by the military, including but not limited to the development of weapons of mass destruction. When exporting the Renesas Electronics products or technology described in this document, you should comply with the applicable export control laws and regulations and follow the procedures required by such laws and regulations.
10. It is the responsibility of the buyer or distributor of Renesas Electronics products, who distributes, disposes of, or otherwise places the product with a third party, to notify such third party in advance of the contents and conditions set forth in this document, Renesas Electronics assumes no responsibility for any losses incurred by you or third parties as a result of unauthorized use of Renesas Electronics products.
11. This document may not be reproduced or duplicated in any form, in whole or in part, without prior written consent of Renesas Electronics.
12. Please contact a Renesas Electronics sales office if you have any questions regarding the information contained in this document or Renesas Electronics products, or if you have any other inquiries.

(Note 1) "Renesas Electronics" as used in this document means Renesas Electronics Corporation and also includes its majority-owned subsidiaries.

(Note 2) "Renesas Electronics product(s)" means any product developed or manufactured by or for Renesas Electronics.

General Precautions in the Handling of MPU/MCU Products

The following usage notes are applicable to all MPU/MCU products from Renesas. For detailed usage notes on the products covered by this document, refer to the relevant sections of the document as well as any technical updates that have been issued for the products.

1. Handling of Unused Pins

Handle unused pins in accordance with the directions given under Handling of Unused Pins in the manual.

- The input pins of CMOS products are generally in the high-impedance state. In operation with an unused pin in the open-circuit state, extra electromagnetic noise is induced in the vicinity of LSI, an associated shoot-through current flows internally, and malfunctions occur due to the false recognition of the pin state as an input signal become possible. Unused pins should be handled as described under Handling of Unused Pins in the manual.

2. Processing at Power-on

The state of the product is undefined at the moment when power is supplied.

- The states of internal circuits in the LSI are indeterminate and the states of register settings and pins are undefined at the moment when power is supplied.
In a finished product where the reset signal is applied to the external reset pin, the states of pins are not guaranteed from the moment when power is supplied until the reset process is completed. In a similar way, the states of pins in a product that is reset by an on-chip power-on reset function are not guaranteed from the moment when power is supplied until the power reaches the level at which resetting has been specified.

3. Prohibition of Access to Reserved Addresses

Access to reserved addresses is prohibited.

- The reserved addresses are provided for the possible future expansion of functions. Do not access these addresses; the correct operation of LSI is not guaranteed if they are accessed.

4. Clock Signals

After applying a reset, only release the reset line after the operating clock signal has become stable. When switching the clock signal during program execution, wait until the target clock signal has stabilized.

- When the clock signal is generated with an external resonator (or from an external oscillator) during a reset, ensure that the reset line is only released after full stabilization of the clock signal. Moreover, when switching to a clock signal produced with an external resonator (or by an external oscillator) while program execution is in progress, wait until the target clock signal is stable.

5. Differences between Products

Before changing from one product to another, i.e. to a product with a different part number, confirm that the change will not lead to problems.

- The characteristics of an MPU or MCU in the same group but having a different part number may differ in terms of the internal memory capacity, layout pattern, and other factors, which can affect the ranges of electrical characteristics, such as characteristic values, operating margins, immunity to noise, and amount of radiated noise. When changing to a product with a different part number, implement a system-evaluation test for the given product.

How to Use This Manual

1. Purpose and Target Readers

This manual describes the API (Application Program Interface) of the Glucose profile (GLP) of the Bluetooth Low Energy protocol stack (BLE software), which is used to develop Bluetooth applications that incorporate the Renesas Bluetooth low energy microcontroller RL78/G1D. It is intended for users designing application systems incorporating this software. A basic knowledge of microcontrollers and Bluetooth low energy is necessary in order to use this manual.

Related documents

The related documents indicated in this publication may include preliminary versions. However, preliminary versions are not marked as such.

Document Name	Document No.
Bluetooth Low Energy Protocol Stack	
User's Manual	R01UW0095E
API Reference Manual: Basics	R01UW0088E
API Reference Manual: FMP	R01UW0089E
API Reference Manual: PXP	R01UW0090E
API Reference Manual: HTP	R01UW0091E
API Reference Manual: BLP	R01UW0092E
API Reference Manual: HOGP	R01UW0093E
API Reference Manual: ScPP	R01UW0094E
API Reference Manual: HRP	R01UW0097E
API Reference Manual: CSCP	R01UW0098E
API Reference Manual: CPP	R01UW0099E
API Reference Manual: GLP	This manual
API Reference Manual: TIP	R01UW0106E
API Reference Manual: RSCP	R01UW0107E
API Reference Manual: ANP	R01UW0108E
API Reference Manual: PASP	R01UW0109E
API Reference Manual: LNP	R01UW0113E
Application Note: Sample Program	R01AN1375E
Application Note: rBLE Command Specification	R01AN1376E

List of Abbreviations and Acronyms

Abbreviation	Full Form	Remark
ANP	Alert Notification Profile	
ANS	Alert Notification Service	
API	Application Programming Interface	
ATT	Attribute Protocol	
BAS	Battery Service	
BB	Base Band	
BD_ADDR	Bluetooth Device Address	
BLE	Bluetooth low energy	
BLP	Blood Pressure Profile	
BLS	Blood Pressure Service	
CPP	Cycling Power Profile	
CPS	Cycling Power Service	
CSCP	Cycling Speed and Cadence Profile	
CSCS	Cycling Speed and Cadence Service	
CSRK	Connection Signature Resolving Key	
CTS	Current Time Service	
DIS	Device Information Service	
EDIV	Encrypted Diversifier	
FMP	Find Me Profile	
GAP	Generic Access Profile	
GATT	Generic Attribute Profile	
GLP	Glucose Profile	
GLS	Glucose Service	
HCI	Host Controller Interface	
HID	Human Interface Device	
HIDS	HID Service	
HOGP	HID over GATT Profile	
HRP	Heart Rate Profile	
HRS	Heart Rate Service	
HTP	Health Thermometer Profile	
HTS	Health Thermometer Service	
IAS	Immediate Alert Service	
IRK	Identity Resolving Key	
L2CAP	Logical Link Control and Adaptation Protocol	
LE	Low Energy	

Abbreviation	Full Form	Remark
LL	Link Layer	
LLS	Link Loss Service	
LNP	Location and Navigation Profile	
LNS	Location and Navigation Service	
LTK	Long Term Key	
MCU	Micro Controller Unit	
MITM	Man-in-the-middle	
MTU	Maximum Transmission Unit	
NDCS	Next DST Change Service	
OOB	Out of Band	
OS	Operating System	
PASP	Phone Alert Status Profile	
PASS	Phone Alert Status Service	
PXP	Proximity Profile	
RF	Radio Frequency	
RSCP	Running Speed and Cadence Profile	
RSCS	Running Speed and Cadence Service	
RSSI	Received Signal Strength Indication	
RTUS	Reference Time Update Service	
ScPP	Scan Parameters Profile	
ScPS	Scan Parameters Service	
SM	Security Manager	
SMP	Security Manager Protocol	
STK	Short Term Key	
TIP	Time Profile	
TK	Temporary Key	
TPS	Tx Power Service	
UART	Universal Asynchronous Receiver Transmitter	
UUID	Universal Unique Identifier	

Abbreviation	Full Form	Remark
APP	Application	
CSI	Clocked Serial Interface	
IIC	Inter-Integrated Circuit	
RSCIP	Renesas Serial Communication Interface Protocol	
VS	Vendor Specific	

All trademarks and registered trademarks are the property of their respective owners.

Bluetooth is a registered trademark of Bluetooth SIG, Inc. U.S.A.

EEPROM is a trademark of Renesas Electronics Corporation.

Windows, Windows NT and Windows XP are registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.

PC/AT is a trademark of International Business Machines Corporation.

Contents

1. Overview.....	1
2. Common Definitions	2
2.1 Service Definitions	2
2.2 Status Definitions.....	4
3. Glucose Profile	5
3.1 Definitions	5
3.2 Functions	18
3.2.1 RBLE_GLP_Sensor_Enable.....	19
3.2.2 RBLE_GLP_Sensor_Disable.....	20
3.2.3 RBLE_GLP_Sensor_Send_Measurements.....	21
3.2.4 RBLE_GLP_Sensor_Send_Measurements_Context	24
3.2.5 RBLE_GLP_Sensor_Send_RA_Control_Point.....	26
3.2.6 RBLE_GLP_Collector_Enable.....	28
3.2.7 RBLE_GLP_Collector_Disable.....	29
3.2.8 RBLE_GLP_Collector_Read_Char	30
3.2.9 RBLE_GLP_Collector_Write_Char	31
3.2.10 RBLE_GLP_Collector_Write_RA_Control_Point.....	32
3.3 Events	34
3.3.1 RBLE_GLP_EVENT_SENSOR_ENABLE_COMP	35
3.3.2 RBLE_GLP_EVENT_SENSOR_DISABLE_COMP	35
3.3.3 RBLE_GLP_EVENT_SENSOR_ERROR_IND	35
3.3.4 RBLE_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_COMP	36
3.3.5 RBLE_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_CONTEXT_COMP	36
3.3.6 RBLE_GLP_EVENT_SENSOR_SEND_RA_CP_COMP	36
3.3.7 RBLE_GLP_EVENT_SENSOR_CHG_RA_CP_IND.....	37
3.3.8 RBLE_GLP_EVENT_SENSOR_CFG_INDNTF_IND	38
3.3.9 RBLE_GLP_EVENT_SENSOR_COMMAND_DISALLOWED_IND	38
3.3.10 RBLE_GLP_EVENT_COLLECTOR_ENABLE_COMP	39
3.3.11 RBLE_GLP_EVENT_COLLECTOR_DISABLE_COMP	40
3.3.12 RBLE_GLP_EVENT_COLLECTOR_ERROR_IND	40
3.3.13 RBLE_GLP_EVENT_COLLECTOR_MEASUREMENTS_NTF	41
3.3.14 RBLE_GLP_EVENT_COLLECTOR_MEASUREMENTS_CONTEXT_NTF.....	43
3.3.15 RBLE_GLP_EVENT_COLLECTOR_RA_CP_IND.....	45

3.3.16	RBLE_GLP_EVENT_COLLECTOR_READ_CHAR_RESPONSE.....	46
3.3.17	RBLE_GLP_EVENT_COLLECTOR_WRITE_CHAR_RESPONSE.....	46
3.3.18	RBLE_GLP_EVENT_COLLECTOR_COMMAND_DISALLOWED_IND	46
3.4	Message Sequence Chart	47
4.	Notes	48
Appendix A How to Read Definition Tables.....		49
Appendix B Referenced Documents		51
Appendix C Terminology		52

1. Overview

This manual describes the API (Application Program Interface) of the Glucose profile (GLP) of the Bluetooth Low Energy protocol stack (BLE software), which is used to develop Bluetooth applications that incorporate Renesas Bluetooth low energy microcontroller RL78/G1D.

For details about the organization and features of BLE software, see the Bluetooth Low Energy Protocol Stack User's Manual.

2. Common Definitions

This section describes the definitions common to the API of each profile.

2.1 Service Definitions

This section describes the common definitions of services used by the API of multiple profiles.

- Declaration of enumerated type for alert level

```
enum RBLE_SVC_ALT_LVL_enum {
    RBLE_SVC_ALERT_NONE = 0x00,           No alert
    RBLE_SVC_ALERT_MILD,                   Mild alert
    RBLE_SVC_ALERT_HIGH                   High alert
};
```

- Declaration of enumerated type for PnP ID characteristic vendor ID field

```
enum RBLE_SVC_PNP_VENDOR_ID_enum {
    RBLE_SVC_SIG_ASSIGNED_ID = 0x01,      Vendor ID assigned by Bluetooth SIG
    RBLE_SVC_USB_ASSIGNED_ID           Vendor ID assigned by USB Implementer's
                                        Forum
};
```

- Declaration of enumerated type for Name Space field of Characteristic Presentation Format descriptor

```
enum RBLE_SVC_PRESEN_NAMESPASE_enum {
    RBLE_SVC_NAMESPACE_SIG = 0x01,        Defined by Bluetooth SIG
};
```

- Declaration of enumerated type for security level of Service

```
enum RBLE_SVC_SEC_LVL_enum {
    RBLE_SVC_SEC_NONE = 0x01,             No security
    RBLE_SVC_SEC_UNAUTH = 0x02,           Require unauthenticated pairing
    RBLE_SVC_SEC_AUTH = 0x04,             Require authenticated pairing
    RBLE_SVC_SEC_AUTZ = 0x08,             Require authorization
    RBLE_SVC_SEC_ENC = 0x10              Require encryption
};
```

- Declaration of enumerated type for connection types

```
enum RBLE_PRF_CON_enum {
    RBLE_PRF_CON_DISCOVERY = 0x00,        Configuration connection performed
                                           when connecting for the first time
    RBLE_PRF_CON_NORMAL              Normal connection performed when
                                           connecting for the second and
                                           subsequent times
};
```

- Declaration of enumerated type for client configuration characteristic value

```
enum RBLE_PRF_CLIENT_CONFIG_enum {  
    RBLE_PRF_STOP_NTFFIND = 0x00,           Stop notification or indication of  
                                              characteristic value.  
    RBLE_PRF_START_NTF,                     Start notification of  
                                              characteristic value.  
    RBLE_PRF_START_IND                      Start indication of  
                                              characteristic value.  
};
```

- Declaration of enumerated type for server configuration characteristic value

```
enum RBLE_PRF_SERVER_CONFIG_enum {  
    RBLE_PRF_STOP_BRD = 0x00,               Stop broadcast of characteristic value.  
    RBLE_PRF_START_BRD                      Start broadcast of characteristic value.  
};
```

2.2 Status Definitions

This section describes the status definitions used by the API of each profile.

- Declaration of enumerated type for rBLE status

```
enum RBLE_STATUS_enum {
    RBLE_OK = 0x00,
    RBLE_PRF_ERR_INVALID_PARAM = 0x90,

    RBLE_PRF_ERR_INEXISTENT_HDL,

    RBLE_PRF_ERR_STOP_DISC_CHAR_MISSING,
    RBLE_PRF_ERR_MULTIPLE_IAS,
    RBLE_PRF_ERR_INCORRECT_PROP,
    RBLE_PRF_ERR_MULTIPLE_CHAR,
    RBLE_PRF_ERR_NOT_WRITABLE,
    RBLE_PRF_ERR_NOT_READABLE,
    RBLE_PRF_ERR_REQ_DISALLOWED,
    RBLE_PRF_ERR_NTF_DISABLED,
    RBLE_PRF_ERR_IND_DISABLED,
    RBLE_PRF_ERR_ATT_NOT_SUPPORTED,

};
```

	Normal operation
	Invalid parameter specified for setting or acquiring a characteristic value
	Invalid handle specified for setting or acquiring a characteristic value
	The characteristic value is missing.
	Multiple IASs exist.
	Incorrect property
	Multiple characteristic values exist.
	Writing is not permitted.
	Reading is not permitted.
	Requesting is not permitted.
	Notification is disabled.
	Indication is disabled.
	The characteristic value is not supported.

Note: Statuses other than the above are described in *API Reference Manual: Basics*.

3. Glucose Profile

This section describes the API of the Glucose profile. The Glucose profile is used to enable a data collection device to obtain data from a glucose sensor.

3.1 Definitions

This section describes the definitions used by the API of the Glucose profile.

- Declaration of enumerated type for GLP event types

```
enum RBLE_GLP_EVENT_TYPE_enum {
    RBLE_GLP_EVENT_SENSOR_ENABLE_COMP = 0x01,
    RBLE_GLP_EVENT_SENSOR_DISABLE_COMP,
    RBLE_GLP_EVENT_SENSOR_ERROR_IND,
    RBLE_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_COMP,
    RBLE_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_CONTEXT_COMP,
    RBLE_GLP_EVENT_SENSOR_SEND_RA_CP_COMP,
    RBLE_GLP_EVENT_SENSOR_CHG_CP_IND,
    RBLE_GLP_EVENT_SENSOR_CFG_INDNTF_IND,
    RBLE_GLP_EVENT_SENSOR_COMMAND_DISALLOWED_IND,
    RBLE_GLP_EVENT_COLLECTOR_ENABLE_COMP = 0x81,
    RBLE_GLP_EVENT_COLLECTOR_DISABLE_COMP,
    RBLE_GLP_EVENT_COLLECTOR_ERROR_IND,
    RBLE_GLP_EVENT_COLLECTOR_MEASUREMENTS_NTF,
    RBLE_GLP_EVENT_COLLECTOR_MEASUREMENTS_CONTEXT_NTF,
}
```

	Sensor enable completion event (Parameter: sensor_enable)
	Sensor disable completion event (Parameter: sensor_disable)
	Sensor error indication event (Parameter: error_ind)
	Measurements send completion event (Parameter: send_measurements)
	Measurements context send completion event (Parameter: send_measurements_context)
	RA control point send completion event (Parameter: send_ra_cp)
	RA control point change indication event (Parameter: glps_chg_ra_cp_ind)
	Characteristic configuration change indication event (Parameter: glps_cfg_indntf_ind)
	Command disallowed indication event (Parameter: cmd_disallowed_ind)
	Collector enable completion event (Parameter: collector_enable)
	Collector disable completion event (Parameter: collector_disable)
	Collector error indication event (Parameter: error_ind)
	Measurements indication event (Parameter: measurements_ntf)
	Measurement context notification event (Parameter: measurements_context_ntf)

```

RBLE_GLP_EVENT_COLLECTOR_RA_CP_IND,          RA control point indication event
                                              (Parameter: ra_cp_ind)

RBLE_GLP_EVENT_COLLECTOR_READ_CHAR_RESPONSE,  Characteristic value read request
                                              response event
                                              (Parameter: rd_char_resp)

RBLE_GLP_EVENT_COLLECTOR_WRITE_CHAR_RESPONSE, Characteristic value write request
                                              response event
                                              (Parameter: wr_char_resp)

RBLE_GLP_EVENT_COLLECTOR_COMMAND_DISALLOWED_IND
                                              Command disallowed indication event
                                              (Parameter: cmd_disallowed_ind)
};

```

- Declaration of data type for GLP event types

```
typedef uint8_t RBLE_GLP_EVENT_TYPE;
```

- Declaration of data type for GLP Sensor event callback function

```
typedef void ( *RBLE_GLPS_EVENT_HANDLER )( RBLE_GLPS_EVENT *event );
```

- Declaration of data type for GLP Collector event callback function

```
typedef void ( *RBLE_GLPC_EVENT_HANDLER )( RBLE_GLPC_EVENT *event );
```

- Declaration of enumerated type for glucose service/device information service characteristic codes

```

enum RBLE_GLPC_RD_CHAR_CODE_enum {
    RBLE_GLPC_RD_MEASUREMENT_CFG = 0x00,          Measurements notification
    RBLE_GLPC_RD_MEASUREMENT_CONTEXT_CFG,         Measurements context notification
    RBLE_GLPC_RD_RA_CP_CFG,                       RA control point indication
    RBLE_GLPC_RD_FEATURE,                         Glucose feature
    RBLE_GLPC_RD_DIS_MANUF,                       Sensor manufacturer name
    RBLE_GLPC_RD_DIS_MODEL,                      Sensor model number
    RBLE_GLPC_RD_DIS_SERNB,                      Sensor serial number
    RBLE_GLPC_RD_DIS_HWREV,                      Sensor hardware revision
    RBLE_GLPC_RD_DIS_FWREV,                      Sensor firmware revision
    RBLE_GLPC_RD_DIS_SWREV,                      Sensor software revision
    RBLE_GLPC_RD_DIS_SYSID,                      Sensor system ID
    RBLE_GLPC_RD_DIS_IEEE,                      Sensor IEEE certification
                                              information
};

```

- Declaration of enumerated type for glucose service characteristic value settings

```

enum RBLE_GLPC_WR_CHAR_CODE_enum {
    RBLE_GLPC_WR_MEASUREMENT_CODE = 0x01,        Glucose measurement
                                              notification setting
    RBLE_GLPC_WR_MEASUREMENT_CONTEXT_CODE,       Glucose measurement context
                                              notification setting
}

```

```

        RBLE_GLPC_WR_RA_CONTROL_POINT_CODE,
        RA control point
        indication setting
    };

```

- Declaration of enumerated type for glucose service characteristic code

```

enum RBLE_GLPC_WR_CHAR_CODE_enum {
    RBLE_GLPC_WR_MEASUREMENT_CODE = 0x01,
    Glucose measurement characteristic
    RBLE_GLPC_WR_MEASUREMENT_CONTEXT_CODE,
    Glucose measurement context
    characteristic
    RBLE_GLPC_WR_RA_CONTROL_POINT_CODE
    RA control point characteristic
};

```

- Declaration of enumerated type for glucose type setting

```

enum RBLE_GLP_TYPE_enum {
    RBLE_GLP_TYPE_CAPILLARY_WHOLE_BLOOD = 0x01,
    Capillary Whole blood
    RBLE_GLP_TYPE_CAPILLARY_PLASMA,
    Capillary Plasma
    RBLE_GLP_TYPE_VENOUS_WHOLE_BLOOD,
    Venous Whole blood
    RBLE_GLP_TYPE_VENOUS_PLASMA,
    Venous Plasma
    RBLE_GLP_TYPE_ARTERIAL_WHOLE_BLOOD,
    Arterial Whole blood
    RBLE_GLP_TYPE_ARTERIAL_PLASMA,
    Arterial Plasma
    RBLE_GLP_TYPE_UNDETERMINED_WHOLE_BLOOD,
    Undetermined Whole blood
    RBLE_GLP_TYPE_UNDETERMINED_PLASMA,
    Undetermined Plasma
    RBLE_GLP_TYPE_ISF,
    Interstitial Fluid (ISF)
    RBLE_GLP_TYPE_CONTROL_SOLUTION
    Control Solution
};

```

- Declaration of enumerated type for glucose sample location setting

```

enum RBLE_GLP_SAMPLELOC_enum {
    RBLE_GLP_SAMPLELOC_FINGER = 0x01,
    Finger
    RBLE_GLP_SAMPLELOC_AST,
    Alternate Site Test (AST)
    RBLE_GLP_SAMPLELOC_EARLOBE,
    Earlobe
    RBLE_GLP_SAMPLELOC_CONTROL_SOLUTION,
    Control solution
    RBLE_GLP_SAMPLELOC_NOT_AVAILABLE
    Sample location value not available
};

```

- Declaration of enumerated type for glucose sensor status annunciation setting

```

enum RBLE_GLP_SENSORSTATUS_enum {
    RBLE_GLP_SENSORSTATUS_DEVICE_BATTERY_LOW = 0x0001,
    Device battery low at time
    of measurement
    RBLE_GLP_SENSORSTATUS_MALFUNCTION_FAULTING = 0x0002,
    Sensor malfunction or faulting
    at time of measurement
    RBLE_GLP_SENSORSTATUS_INSUFFICIENT = 0x0004,
    Sample size for blood or control
    solution insufficient at time
    of measurement
    RBLE_GLP_SENSORSTATUS_STRIP_INSERTION_ERROR = 0x0008,

```



```

        Strip insertion error
    RBLE_GLP_SENSORSTATUS_STRIP_TYPE_INCORRECT = 0x0010,

        Strip type incorrect for device
    RBLE_GLP_SENSORSTATUS_RESULT_HIGH      = 0x0020,    Sensor result higher than
                                                    the device can process
    RBLE_GLP_SENSORSTATUS_RESULT_LOW = 0x0040,    Sensor result lower than
                                                    the device can process
    RBLE_GLP_SENSORSTATUS_TEMPERATURE_HIGH = 0x0080,    Sensor temperature too high
                                                    for valid test/result at time
                                                    of measurement
    RBLE_GLP_SENSORSTATUS_TEMPERATURE_LOW = 0x0100,    Sensor temperature too low
                                                    for valid test/result at time
                                                    of measurement
    RBLE_GLP_SENSORSTATUS_READ_INTERRUPTED = 0x0200,    Sensor read interrupted because
                                                    strip was pulled too soon at time
                                                    of measurement.

    RBLE_GLP_SENSORSTATUS_GENERAL_DEVICE_FAULT = 0x0400,

        General device fault has occurred
        in the sensor.

    RBLE_GLP_SENSORSTATUS_TIME_FAULT = 0x0800

        Time fault has occurred in
        the sensor and time
        may be inaccurate.
};

```

- Declaration of enumerated type for glucose carbohydrate ID setting

```

enum RBLE_GLP_CARBOHYDRATEID_enum {
    RBLE_GLP_CARBOHYDRATEID_BREAKFAST = 0x01,    Breakfast
    RBLE_GLP_CARBOHYDRATEID_LUNCH,              Lunch
    RBLE_GLP_CARBOHYDRATEID_DINNER,              Dinner
    RBLE_GLP_CARBOHYDRATEID_SNACK,               Snack
    RBLE_GLP_CARBOHYDRATEID_DRINK,               Drink
    RBLE_GLP_CARBOHYDRATEID_SUPPER,              Supper
    RBLE_GLP_CARBOHYDRATEID_BRUNCH              Brunch
};

```

- Declaration of enumerated type for glucose meal setting

```

enum RBLE_GLP_MEAL_enum {
    RBLE_GLP_MEAL_PREPRANDIAL = 0x01,    Preprandial (before meal)
    RBLE_GLP_MEAL_POSTPRANDIAL,          Postprandial (after meal)
    RBLE_GLP_MEAL_FASTING,               Fasting
    RBLE_GLP_MEAL_CASUAL,                Casual (snacks, drinks, etc.)
    RBLE_GLP_MEAL_BEDTIME                Bedtime
};

```

- Declaration of enumerated type for glucose tester setting

```

enum RBLE_GLP_TESTER_enum {
    RBLE_GLP_TESTER_SELF = 0x01,        Self
    RBLE_GLP_TESTER_HEALTH_CARE_PRO,     Health care professional
    RBLE_GLP_TESTER_LAB_TEST,            Lab test
};

```

```

        RBLE_GLP_TESTER_NOT_AVAILABLE           Tester value not available
    };

```

- Declaration of enumerated type for glucose health setting

```

enum RBLE_GLP_HEALTH_enum {
    RBLE_GLP_HEALTH_MINOR_ISSUE = 0x01,           Minor health issues
    RBLE_GLP_HEALTH_MAJOR_ISSUE,                 Major health issues
    RBLE_GLP_HEALTH_DURING_MENSES,              During menses
    RBLE_GLP_HEALTH_UNDER_STRESS,               Under stress
    RBLE_GLP_HEALTH_NO_ISSUE,                   No health issues
    RBLE_GLP_HEALTH_NOT_AVAILABLE               Health value not available
};

```

- Declaration of enumerated type for glucose medication ID setting

```

enum RBLE_GLP_MEDICATIONID_enum {
    RBLE_GLP_MEDICATIONID_RAPID_INSULIN = 0x01,   Rapid acting insulin
    RBLE_GLP_MEDICATIONID_SHORT_INSULIN,         Short acting insulin
    RBLE_GLP_MEDICATIONID_INTERMEDIATE_INSULIN,  Intermediate acting insulin
    RBLE_GLP_MEDICATIONID_LONG_INSULIN,          Long acting insulin
    RBLE_GLP_MEDICATIONID_PREMIXED_INSULIN       Pre-mixed insulin
};

```

- Declaration of enumerated type for RA control point characteristic operation code setting

```

enum RBLE_GLP_OPCODE_enum {
    RBLE_GLP_OPCODE_REPORT_RECORDS = 0x01,       Report stored records
    RBLE_GLP_OPCODE_DELETE_RECORDS,             Delete stored records
    RBLE_GLP_OPCODE_ABORT_OPERATION,            Abort operation
    RBLE_GLP_OPCODE_REPORT_RECORDS_NUMBER,      Report number of stored records
    RBLE_GLP_OPCODE_NUMBER_RECORDS_RESPONSE,   Number of stored records response
    RBLE_GLP_OPCODE_RESPONSE_CODE              Response code
};

```

- Declaration of enumerated type for RA control point characteristic operator setting

```

enum RBLE_GLP_OPERATOR_enum {
    RBLE_GLP_OPERATOR_NULL = 0x00,              Null
    RBLE_GLP_OPERATOR_ALL_RECORDS,              All records
    RBLE_GLP_OPERATOR_LESS,                     Less than or equal to
    RBLE_GLP_OPERATOR_GREATER,                  Greater than or equal to
    RBLE_GLP_OPERATOR_WITHIN_RANGE,             Within range of (inclusive)
    RBLE_GLP_OPERATOR_FIRST_RECORD,             First record (i.e. oldest record)
    RBLE_GLP_OPERATOR_LAST_RECORD,              Last record (i.e. most recent
record)
};

```

- Declaration of enumerated type for RA control point characteristic response setting

```

enum RBLE_GLP_OPERAND_RESPONSE_CODE_enum {

```

```

    RBLE_GLP_OPERAND_SUCCESS = 0x01,
    RBLE_GLP_OPERAND_OPCODE_NOT_SUPPORTED,
    RBLE_GLP_OPERAND_INVALID_OPERATOR,
    RBLE_GLP_OPERAND_OPERATOR_NOT_SUPPORTED,
    RBLE_GLP_OPERAND_INVALID_OPERAND,
    RBLE_GLP_OPERAND_NO_RECORD,
    RBLE_GLP_OPERAND_ABORT_UNSUCCESSFUL,
    RBLE_GLP_OPERAND_NOT_COMPLETED,
    RBLE_GLP_OPERAND_NOT_SUPPORTED
};

```

	Success
	Op Code not supported
	Invalid operator
	Operator not supported
	Invalid operand
	No records found
	Abort unsuccessful
	Procedure not completed
	Operand not supported

- Glucose service characteristic information structures

```

typedef struct RBLE_GLP_SENSOR_PARAM_t {
    uint16_t      glp_meas_ntf_en;
    uint16_t      glp_meas_context_ntf_en;
    uint16_t      ra_cp_ind_en;
}RBLE_GLP_SENSOR_PARAM;

```

	Glucose measurement notification configuration value
	Glucose measurement context notification configuration value
	RA control point indication configuration value

- Date and time information structures

```

typedef struct RBLE_DATE_TIME_t{
    uint16_t      year;
    uint8_t       month;
    uint8_t       day;
    uint8_t       hour;
    uint8_t       min;
    uint8_t       sec;
    uint8_t       reserved;
}RBLE_DATE_TIME;

```

	Year
	Month
	Day
	Hour
	Minute
	Second
	Reserved

- Glucose measurement information structures

```

typedef struct RBLE_GLP_MEASUREMENTS_INFO_t {
    uint8_t      flags;
    uint8_t      reserved;
    uint16_t     seq_num;
    RBLE_DATE_TIME stamp;
    int16_t      time_offset;
    int16_t      concentration;
    uint8_t      type;
    uint8_t      sample_location;
    uint16_t     sensor_status_annun;
} RBLE_GLP_MEASUREMENTS_INFO;

```

	Data field flag
	Reserved
	Sequence number
	Time stamp
	Time offset
	Glucose concentration (kg/L or mol/L)
	Type
	Sample location
	Sensor status annunciation

- Glucose measurement context information structure

```
typedef struct RBLE_GLP_MEASUREMENTS_CONTEXT_INFO_t {
    uint8_t      flags;                Data field flag
    uint8_t      reserved1;            Reserved
    uint16_t     seq_num;               Sequence number
    uint8_t      ex_flags;              Extended flags
    uint8_t      carbohydrate_id;       Carbohydrate ID
    int16_t      carbohydrate_kg;        Carbohydrate - units of kilograms
    uint8_t      meal;                  Meal
    uint8_t      tester;                 Tester
    uint8_t      health;                 Health
    uint8_t      reserved2;              Reserved
    uint16_t     exercise_duration;      Exercise duration
    uint8_t      exercise_intensity;     Exercise intensity
    uint8_t      medication_id;          Medication ID
    int16_t      medication;              Medication (kg or Litter)
    int16_t      HbA1c;                  HbA1c
} RBLE_GLP_MEASUREMENTS_CONTEXT_INFO;
```

- RA control point setting structure

```
typedef struct RBLE_GLP_RA_CONTROL_POINT_INFO_t{
    uint8_t      OpCode;                Op Code
    uint8_t      racp_operator;           Operator
    uint8_t      operand_value;           Operand
    uint8_t      reserved;                Reserved
    uint16_t     min_sequence_num;         Minimum sequence number
                                           to specify a range of records
    uint16_t     max_sequence_num;         Maximum sequence number
                                           to specify a range of records
    RBLE_DATE_TIME min_stamp;              Minimum time stamp
                                           to specify a range of records
    RBLE_DATE_TIME max_stamp;              Minimum time stamp
                                           to specify a range of records
} RBLE_GLP_RA_CONTROL_POINT_INFO;
```

- RA control point response structure

```
typedef struct RBLE_GLP_RA_CONTROL_POINT_IND_INFO_t {
    uint8_t      OpCode;                Op Code
    uint8_t      racp_operator;           Operator
    uint16_t     num_of_records;          Number of records
    uint8_t      request_op_code;         Request Op Code
    uint8_t      response_code_value;     Response code value
} RBLE_GLP_RA_CONTROL_POINT_IND_INFO;
```

- Glucose service content structures

```
typedef struct RBLE_GLS_CONTENT_t{
    uint16_t     shdl;                    Glucose service start handle
}
```

uint16_t	ehdl;	Glucose service end handle
uint16_t	glucose_meas_char_hdl;	Glucose measurement characteristic handle
uint16_t	glucose_meas_val_hdl;	Glucose measurement characteristic value handle
uint16_t	glucose_meas_cfg_hdl;	Glucose measurement client characteristic configuration descriptor handle
uint8_t	glucose_meas_prop;	Glucose measurement characteristic property
uint8_t	reserved;	Reserved
uint16_t	glucose_meas_context_char_hdl;	Glucose measurement context characteristic handle
uint16_t	glucose_meas_context_val_hdl;	Glucose measurement context characteristic value handle
uint16_t	glucose_meas_context_cfg_hdl;	Glucose measurement context client characteristic configuration descriptor handle
uint8_t	glucose_meas_context_prop;	Glucose measurement context characteristic property
uint8_t	reserved2;	Reserved
uint16_t	glucose_feature_char_hdl;	Glucose feature characteristic handle
uint16_t	glucose_feature_val_hdl;	Glucose feature characteristic value handle
uint8_t	glucose_feature_prop;	Glucose feature characteristic property
uint8_t	reserved3;	Reserved
uint16_t	glucose_ra_cp_char_hdl;	RA control point characteristic handle
uint16_t	glucose_ra_cp_val_hdl;	RA control point characteristic value handle
uint16_t	glucose_ra_cp_cfg_hdl;	RA control point client characteristic configuration descriptor handle
uint8_t	glucose_ra_cp_prop;	RA control point characteristic property
uint8_t	reserved4;	Reserved

}RBLE_GLS_CONTENT;

- Device information service content structures

```
typedef struct RBLE_DIS_CONTENT_t {
    uint16_t    shdl;                Device information service start handle
    uint16_t    ehdl;                Device information service end handle
    uint16_t    sys_id_char_hdl;     System ID characteristic handle
    uint16_t    sys_id_val_hdl;      System ID characteristic value handle
    uint8_t     sys_id_prop;         System ID characteristic property
    uint8_t     reserved;            Reserved
    uint16_t    model_nb_char_hdl;   Model number characteristic handle
}
```

uint16_t	model_nb_val_hdl;	Model number characteristic value handle
uint8_t	model_nb_prop;	Model number characteristic property
uint8_t	reserved2;	Reserved
uint16_t	serial_nb_char_hdl;	Serial number characteristic handle
uint16_t	serial_nb_val_hdl;	Serial number characteristic value handle
uint8_t	serial_nb_prop;	Serial number characteristic property
uint8_t	reserved3;	Reserved
uint16_t	fw_rev_char_hdl;	Firmware revision characteristic handle
uint16_t	fw_rev_val_hdl;	Firmware revision characteristic value handle
uint8_t	fw_rev_prop;	Firmware revision characteristic property
uint8_t	reserved4;	Reserved
uint16_t	hw_rev_char_hdl;	Hardware revision characteristic handle
uint16_t	hw_rev_val_hdl;	Hardware revision characteristic value handle
uint8_t	hw_rev_prop;	Hardware revision characteristic property
uint8_t	reserved5;	Reserved
uint16_t	sw_rev_char_hdl;	Software revision characteristic handle
uint16_t	sw_rev_val_hdl;	Software revision characteristic value handle
uint8_t	sw_rev_prop;	Software revision characteristic property
uint8_t	reserved6;	Reserved
uint16_t	manuf_name_char_hdl;	Manufacturer name characteristic handle
uint16_t	manuf_name_val_hdl;	Manufacturer name characteristic value handle
uint8_t	manuf_name_prop;	Manufacturer name characteristic property
uint8_t	reserved7;	Reserved
uint16_t	ieee_certif_char_hdl;	IEEE certification characteristic handle
uint16_t	ieee_certif_val_hdl;	IEEE certification characteristic value handle
uint8_t	ieee_certif_prop;	IEEE certification characteristic property
uint8_t	reserved8;	Reserved
}RBLE_DIS_CONTENT;		

- GLP Sensor event parameter structures

```
typedef struct RBLE_GLPS_EVENT_t {
    RBLE_GLP_EVENT_TYPE      type;           GLP event type
    uint8_t                  reserved;       Reserved
    union Event_Gls_Parameter_u {
        Generic event
        RBLE_STATUS          status;        Status

        Sensor enable completion event
        struct RBLE_GLP_Sensor_Enable_t{
            RBLE_STATUS      status;        Status
            uint8_t          reserved;      Reserved
            uint16_t         conhdl;        Connection handle
        }sensor_enable;

        Sensor disable completion event
        struct RBLE_GLP_Sensor_Disable_t{
            uint16_t         conhdl;        Connection handle
            RBLE_GLP_SENSOR_PARAM sensor_info; Glucose service information
        }sensor_disable;

        Sensor error indication event
        struct RBLE_GLP_Sensor_Error_Ind_t{
            uint16_t         conhdl;        Connection handle
            RBLE_STATUS      status;        Status
        }error_ind;

        Sensor measurements send completion event
        struct RBLE_GLP_Sensor_Send_Measurements_t{
            uint16_t         conhdl;        Connection handle
            RBLE_STATUS      status;        Status
        }send_measurements;

        Sensor measurement context send completion event
        struct RBLE_GLP_Sensor_Send_Measurements_Context_t{
            uint16_t         conhdl;        Connection handle
            RBLE_STATUS      status;        Status
        }send_measurements_context;

        Sensor RA control point send completion event
        struct RBLE_GLP_Sensor_Send_RA_Control_Point_t{
            uint16_t         conhdl;        Connection handle
            RBLE_STATUS      status;        Status
        }send_ra_cp;

        Sensor RA control point change indication event
    };
};
```

```

struct RBLE_GLP_Sensor_Chg_Ra_Cp_Ind_t{
    uint16_t          conhdl;          Connection handle
    RBLE_GLP_RA_CONTROL_POINT_INFO ra_cp_info; RA control point information
}glps_chg_ra_cp_ind;

```

Sensor configuration characteristic value indication event

```

struct RBLE_GLP_Sensor_Cfg_Indntf_Ind_t{
    uint16_t          conhdl;          Connection handle
    uint8_t           char_code;       Characteristic value code
    uint8_t           reserved;        Reserved
    uint16_t          cfg_val;         Configuration characteristic
                                        value
}glps_cfg_indntf_ind;

```

Sensor command disallowed indication event

```

struct RBLE_GLP_Sensor_Command_Disallowed_Ind_t{
    RBLE_STATUS       status;          Status
    uint8_t           reserved;        Reserved
    uint16_t          opcode;          Opcode
}cmd_disallowed_ind;
} param;
} RBLE_GLPS_EVENT;

```

- GLP Collector event parameter structures

```

typedef struct RBLE_GLPC_EVENT_t {
    RBLE_GLP_EVENT_TYPE    type;          GLP event type
    uint8_t                reserved;       Reserved
    union Event_Glc_Parameter_u {
        Generic event
        RBLE_STATUS        status;          Status

        Collector enable completion event
        struct RBLE_GLP_Collector_Enable_t{
            RBLE_STATUS     status;          Status
            uint8_t         reserved;        Reserved
            uint16_t        conhdl;          Connection handle
            RBLE_GLS_CONTENT gls;           Glucose service content
            RBLE_DIS_CONTENT dis;           Device information service
                                                content
        }collector_enable;

        Collector disable completion event
        struct RBLE_GLP_Collector_Disable_t{
            RBLE_STATUS     status;          Status
            uint8_t         reserved;        Reserved
            uint16_t        conhdl;          Connection handle
        }collector_disable;
    };
};

```


Collector error indication event

```
struct RBLE_GLP_Collector_Error_Ind_t{
    RBLE_STATUS          status;          Status
    uint8_t              reserved;        Reserved
    uint16_t             conhdl;          Connection handle
}error_ind;
```

Collector measurement information indication event

```
struct RBLE_GLP_Collector_Measurements_Ntf_t{
    uint16_t             conhdl;          Connection handle
    RBLE_GLP_MEASUREMENTS_INFO  measure_info;  Sensor measurement information
}measurements_ntf;
```

Collector measurement context information indication event

```
struct RBLE_GLP_Collector_Measurements_Context_Ntf_t{
    uint16_t             conhdl;          Connection handle
    RBLE_GLP_MEASUREMENTS_CONTEXT_INFO  measure_context_info;
                                          Sensor measurement context
                                          information
}measurements_context_ntf;
```

Collector RA control point information indication event

```
struct RBLE_GLP_Collector_RA_CP_Ind_t{
    uint16_t             conhdl;          Connection handle
    RBLE_GLP_RA_CONTROL_POINT_IND_INFO  ra_cp_ind_info;
                                          RA control point information
}ra_cp_ind;
```

Collector characteristic value read request response event

```
struct RBLE_GLP_Collector_Read_Char_Response_t{
    uint16_t             conhdl;          Connection handle
    uint8_t              att_code;        Status
    uint8_t              reserved ;        Reserved
    RBLE_ATT_INFO_DATA   data;            Acquired characteristic data
}rd_char_resp;
```

Collector characteristic value write request response event

```
struct RBLE_GLP_Collector_Write_Char_Response_t{
    uint16_t             conhdl;          Connection handle
    uint8_t              att_code;        Status
}wr_char_resp;
```

Collector command disallowed indication event

```
struct RBLE_GLP_Collector_Command_Disallowed_Ind_t{
    RBLE_STATUS          status;          Status
    uint8_t              reserved;        Reserved
}
```

```
        uint16_t          opcode;          Opcode
    }cmd_disallowed_ind;
} param;
} RBLE_GLPC_EVENT;
```

3.2 Functions

The following table shows the API functions defined for the GLP of rBLE and the following sections describe the API functions in detail.

Table 3-1 API Functions Used by the GLP

RBLE_GLP_Sensor_Enable	Enables the Sensor role.
RBLE_GLP_Sensor_Disable	Disables the Sensor role.
RBLE_GLP_Sensor_Send_Measurements	Sends measurements information.
RBLE_GLP_Sensor_Send_Measurements_Context	Sends measurement context information.
RBLE_GLP_Sensor_Send_RA_Control_Point	Sends RA control point information.
RBLE_GLP_Collector_Enable	Enables the Collector role.
RBLE_GLP_Collector_Disable	Disables the Collector role.
RBLE_GLP_Collector_Read_Char	Reads the characteristic value.
RBLE_GLP_Collector_Write_Char	Writes the characteristic value.
RBLE_GLP_Collector_Write_RA_Control_Point	Sets RA control point.

3.2.1 RBLE_GLP_Sensor_Enable

RBLE_STATUS RBLE_GLP_Sensor_Enable(uint16_t conhdl, uint8_t sec_lvl, uint8_t con_type, RBLE_GLP_SENSOR_PARAM *param, RBLE_GLPS_EVENT_HANDLER call_back)

This function enables the GLP Sensor role.

If the measurement result notification, the measurement context information notification or the RA control point indication has been specified from the Collector, set the indication/notification setting parameter to 0 to configure the connection. If this setting or information has been specified from the Sensor, perform a normal connection in accordance with the indication/notification setting parameter.

The result is reported by using the Sensor role enable completion event RBLE_GLP_EVENT_SENSOR_ENABLE_COMP.

Parameters:

<i>conhdl</i>	Connection handle		
<i>sec_lvl</i>	Security level		
<i>con_type</i>	RBLE_PRF_CON_DISCOVERY		Configuration connection
	RBLE_PRF_CON_NORMAL		Normal connection
<i>*param</i>	<i>glp_meas_ntf_en</i>	RBLE_PRF_STOP_NTFFIND	Stop notification of measurement information.
		RBLE_PRF_START_NTF	Start notification of measurement information.
	<i>glp_meas_context_ntf_en</i>	RBLE_PRF_STOP_NTFFIND	Stop notification of measurement context information.
		RBLE_PRF_START_NTF	Start notification of measurement context information.
	<i>ra_cp_ind_en</i>	RBLE_PRF_STOP_NTFFIND	Stop indication of RA control point.
		RBLE_PRF_START_IND	Start indication of RA control point.
<i>call_back</i>	Specify the callback function that reports the GLP event.		

Return:

<i>RBLE_OK</i>	Success
<i>RBLE_ERR</i>	Error occurred in Sensor role enable processing
<i>RBLE_PARAM_ERR</i>	Invalid parameter
<i>RBLE_STATUS_ERROR</i>	Not executable because the rBLE mode is other than RBLE_MODE_ACTIVE.

3.2.2 RBLE_GLP_Sensor_Disable

RBLE_STATUS RBLE_GLP_Sensor_Disable(uint16_t conhdl)		
This function disables the GLP Sensor role. The result is reported by using the Sensor role disable completion event RBLE_GLP_EVENT_SENSOR_DISABLE_COMP.		
Parameters:		
	<i>conhdl</i>	Connection handle
Return:		
	<i>RBLE_OK</i>	Success
	<i>RBLE_STATUS_ERROR</i>	Not executable because the rBLE mode is other than RBLE_MODE_ACTIVE.

3.2.3 RBLG_GLP_Sensor_Send_Measurements

RBLG_STATUS RBLG_GLP_Sensor_Send_Measurements(uint16_t conhdl,
RBLG_GLP_MEASUREMENTS_INFO *measurements_info)

This function sends the measured value data from the sensor.

The result is reported by using the Sensor measurements send completion event

RBLG_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_COMP.

When sending the measured value data continuously, send the next measured value data after completion event RBLG_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_COMP is reported.

Parameters:

<i>conhdl</i>	Connection handle		
<i>*measurements_info</i>	<i>flags</i>	Flag that defines whether there is a data field in the characteristic value or not	
	<i>seq_num</i>	Sequence number	
	<i>stamp</i>	Time stamp	
		<i>year</i>	Year
		<i>month</i>	Month
		<i>day</i>	Day
		<i>hour</i>	Hour
		<i>min</i>	Minute
		<i>sec</i>	Second
	<i>time_offset</i>	Time offset	
	<i>concentration</i>	Glucose Concentration (kg/L or mol/L)	
	<i>type</i>	Type	
		RBLG_GLP_TYPE_CAPILARY_WHOLE_BLOOD	Capillary Whole blood
		RBLG_GLP_TYPE_CAPILARY_PLASMA	Capillary Plasma
		RBLG_GLP_TYPE_VENOUS_WHOLE_BLOOD	Venous Whole blood
		RBLG_GLP_TYPE_VENOUS_PLASMA	Venous Plasma
		RBLG_GLP_TYPE_ARTERIAL_WHOLE_BLOOD	Arterial Whole blood
		RBLG_GLP_TYPE_ARTERIAL_PLASMA	Arterial Plasma
		RBLG_GLP_TYPE_UNDETERMINED_WHOLE_BLOOD	Undetermined Whole blood
		RBLG_GLP_TYPE_UNDETERMINED_PLASMA	Undetermined Plasma
		RBLG_GLP_TYPE_ISF	Interstitial Fluid (ISF)
		RBLG_GLP_TYPE_CONTROL_SOLUTION	Control Solution
	<i>sample_location</i>	Sample location	
		RBLG_GLP_SAMPLELOC_FINGER	Finger

RBLE_STATUS RBLE_GLP_Sensor_Send_Measurements(uint16_t conhdl, RBLE_GLP_MEASUREMENTS_INFO *measurements_info)						
			RBLE_GLP_SAMPLELOC_AST	Alternate Site Test (AST)		
			RBLE_GLP_SAMPLELOC_EARLOBE	Earlobe		
			RBLE_GLP_SAMPLELOC_CONTROL_SOLUTION	Control solution		
			RBLE_GLP_SAMPLELOC_NOT_AVAILABLE	Sample Location value not available		
		Sensor_status_annun	Sensor status annunciation			
			RBLE_GLP_SENSORSTATUS_DEVICE_BATTERY_LOW	Device battery low at time of measurement		
			RBLE_GLP_SENSORSTATUS_MALFUNCTION_FAULTING	Sensor malfunction or faulting at time of measurement		
			RBLE_GLP_SENSORSTATUS_INSUFFICIENT	Sample size for blood or control solution insufficient at time of measurement		
			RBLE_GLP_SENSORSTATUS_STRIP_INSERTION_ERROR	Strip insertion error		
			RBLE_GLP_SENSORSTATUS_STRIP_TYPE_INCORRECT	Strip type incorrect for device		
			RBLE_GLP_SENSORSTATUS_RESULT_HIGH	Sensor result higher than the device can process		
			RBLE_GLP_SENSORSTATUS_RESULT_LOW	Sensor result lower than the device can process		
			RBLE_GLP_SENSORSTATUS_TEMPERATURE_HIGH	Sensor temperature too high for valid test/result at time of measurement		
			RBLE_GLP_SENSORSTATUS_TEMPERATURE_LOW	Sensor temperature too low for valid test/result at time of measurement		
			RBLE_GLP_SENSORSTATUS_READ_INTERRUPTED	Sensor read interrupted because strip was pulled too soon at time of measurement		
			RBLE_GLP_SENSORSTATUS_GENERAL_DEVICE_FAULT	General device fault has occurred in the sensor		
			RBLE_GLP_SENSORSTATUS_TIME_FAULT	Time fault has occurred in the sensor and time may be inaccurate		
Return:						
RBLE_OK		Success				

RBLE_STATUS RBLE_GLP_Sensor_Send_Measurements(uint16_t conhdl, RBLE_GLP_MEASUREMENTS_INFO *measurements_info)		
	<i>RBLE_STATUS_ERROR</i>	Not executable because the rBLE mode is other than RBLE_MODE_ACTIVE.

3.2.4 RBLE_GLP_Sensor_Send_Measurements_Context

```
RBLE_STATUS RBLE_GLP_Sensor_Send_Measurements_Context(uint16_t conhdl,
  RBLE_GLP_MEASUREMENTS_INFO *measurements_context_info)
```

This function sends the measurement context data from the sensor.

The result is reported by using the Sensor measurements send completion event

RBLE_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_CONTEXT_COMP.

When sending the measurement context data continuously, send the next measurement context data after completion event RBLE_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_CONTEXT_COMP is reported.

Parameters:

conhdl	Connection handle		
*measurements_context_info	flags	Flag that defines whether there is a data field in the characteristic value or not	
	seq_num	Sequence number	
	ex_flags	Extended flags	
	carbohydrate_id	Carbohydrate ID	
		RBLE_GLP_CARBOHYD RATEID_BREAKFAST	Breakfast
		RBLE_GLP_CARBOHYD RATEID_LUNCH	Lunch
		RBLE_GLP_CARBOHYD RATEID_DINNER	Dinner
		RBLE_GLP_CARBOHYD RATEID_SNACK	Snack
		RBLE_GLP_CARBOHYD RATEID_DRINK	Drink
		RBLE_GLP_CARBOHYD RATEID_SUPPER	Supper
		RBLE_GLP_CARBOHYD RATEID_BRUNCH	Brunch
	carbohydrate_kg	Carbohydrate – units of kilograms	
	meal	Meal	
		RBLE_GLP_MEAL_PREP RANDIAL	Preprandial (before meal)
		RBLE_GLP_MEAL_POST PRANDIAL	Postprandial (after meal)
		RBLE_GLP_MEAL_FAST ING	Fasting
		RBLE_GLP_MEAL_CASU AL	Casual (snacks, drinks, etc.)
		RBLE_GLP_MEAL_BEDT IME	Bedtime
	tester	Tester	
		RBLE_GLP_TESTER_SE LF	Self
		RBLE_GLP_TESTER_HE ALTH_CARE_PRO	Health Care Professional
		RBLE_GLP_TESTER_LA B_TEST	Lab test

RBLE_STATUS RBLE_GLP_Sensor_Send_Measurements_Context(uint16_t conhdl, RBLE_GLP_MEASUREMENTS_INFO *measurements_context_info)					
			RBLE_GLP_TESTER_NOT_AVAILABLE	Tester value not available	
		health	Health		
			RBLE_GLP_HEALTH_MINOR_ISSUE	Minor health issues	
			RBLE_GLP_HEALTH_MAJOR_ISSUE	Major health issues	
			RBLE_GLP_HEALTH_DURING_MENSES	During menses	
			RBLE_GLP_HEALTH_UNDER_STRESS	Under stress	
			RBLE_GLP_HEALTH_NO_ISSUE	No health issues	
			RBLE_GLP_HEALTH_NOT_AVAILABLE	Health value not available	
		exercise_duration	Exercise Duration		
		exercise_intensity	Exercise Intensity		
		medication_id	Medication ID		
			RBLE_GLP_MEDICATION_ID_RAPID_INSULIN	Rapid acting insulin	
			RBLE_GLP_MEDICATION_ID_SHORT_INSULIN	Short acting insulin	
			RBLE_GLP_MEDICATION_ID_INTERMEDIATE_INSULIN	Intermediate acting insulin	
			RBLE_GLP_MEDICATION_ID_LONG_INSULIN	Long acting insulin	
			RBLE_GLP_MEDICATION_ID_PREMIXED_INSULIN	Pre-mixed insulin	
		medication	Medication (kg or litter)		
		HbA1c	HbA1c		
Return:					
RBLE_OK		Success			
RBLE_STATUS_ERROR		Not executable because the rBLE mode is other than RBLE_MODE_ACTIVE.			

3.2.5 RBLG_GL_P_Sensor_Send_RA_Control_Point

```
RBLE_STATUS RBLE_GLP_Sensor_Send_RA_Control_Point(uint16_t conhdl,
RBLE_GLP_RA_CONTROL_POINT_IND_INFO *ra_cp_info)
```

This function sends RA control point information from the sensor. After executing an operation code that is written to the operation of RA control points from the Collector, respond by using this API.

If RBLE_GLP_OPCODE_REPORT_RECORDS has been written to RA control point from the Collector, respond by setting RBLE_GLP_OPCODE_RESPONSE_CODE to OpCode, after sending the record to the Collector by calling RBLE_GLP_Sensor_Send_Measurements and RBLE_GLP_Sensor_Send_Measurements_Context.

If RBLE_GLP_OPCODE_DELETE_RECORDS has been written to RA control point from the Collector, respond by setting RBLE_GLP_OPCODE_RESPONSE_CODE to OpCode, after deleting records.

If RBLE_GLP_OPCODE_ABORT_OPERATION has been written to RA control point from the Collector, respond by setting RBLE_GLP_OPCODE_RESPONSE_CODE to OpCode, after aborting the operation being performed.

If RBLE_GLP_OPCODE_REPORT_RECORDS_NUMBER has been written to RA control point from the Collector, respond by setting RBLE_GLP_OPCODE_NUMBER_RECORDS_RESPONSE to OpCode and setting a number of records to num_of_records.

Also, set the operation code received from the collector into the request_op_code, and set the execution result of the operation into the response_code_value.

The result is reported by using the Sensor role measurements send completion event

RBLE_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_CONTEXT_COMP.

Parameters:

<i>conhdl</i>	Connection handle		
<i>*ra_cp_info</i>	<i>OpCode</i>	RBLE_GLP_OPCODE_NUMBER_RECORDS_RESPONSE	Number of stored records response
		RBLE_GLP_OPCODE_RESPONSE_CODE	Response Code
	<i>racp_operator</i>	RBLE_GLP_OPERATOR_NULL	Null
	<i>num_of_records</i>	Number of records	
	<i>request_op_code</i>	RBLE_GLP_OPCODE_REPORT_RECORDS	Report stored records
		RBLE_GLP_OPCODE_DELETE_RECORDS	Delete stored records
		RBLE_GLP_OPCODE_ABORT_OPERATION	Abort operation
		RBLE_GLP_OPCODE_REPORT_RECORDS_NUMBER	Report number of stored records
	<i>response_code_value</i>	RBLE_GLP_OPERAND_SUCCESS	Success
		RBLE_GLP_OPERAND_OPCODE_NOT_SUPPORTED	Op Code not supported
		RBLE_GLP_OPERAND_INVALID_OPERATOR	Invalid Operator
		RBLE_GLP_OPERAND_OPERATOR_NOT_SUPPORTED	Operator not supported
		RBLE_GLP_OPERAND_INVALID_OPERAND	Invalid Operand

RBLE_STATUS RBLE_GLP_Sensor_Send_RA_Control_Point(uint16_t conhdl, RBLE_GLP_RA_CONTROL_POINT_IND_INFO *ra_cp_info)				
			RBLE_GLP_OPERAND_NO_RECORD	No records found
			RBLE_GLP_OPERAND_ABORT_UNSUCCESSFUL	Abort unsuccessful
			RBLE_GLP_OPERAND_NOT_COMPLETED	Procedure not completed
			RBLE_GLP_OPERAND_NOT_SUPPORTED	Operand not supported
Return:				
		RBLE_OK	Success	
		RBLE_STATUS_ERROR	Not executable because the rBLE mode is other than RBLE_MODE_ACTIVE.	

3.2.6 RBLE_GLP_Collector_Enable

```

RBLE_STATUS RBLE_GLP_Collector_Enable(uint16_t conhdl, uint8_t con_type,
RBLE_GLS_CONTENT *gls, RBLE_DIS_CONTENT *dis, RBLE_GLPC_EVENT_HANDLER call_back)

```

This function enables the GLP Collector role and starts access to the service exposed by the GLP Sensor. The result is reported by using the Collector role enable completion event `RBLE_GLP_EVENT_COLLECTOR_ENABLE_COMP`.

When starting access to the service exposed by a Sensor to be connected for the first time, set 0 to the parameters of the service to configure the connection and to discover the service for the Sensor. If the handle information about the discovered service is saved and is used when the Sensor is connected normally for a second or subsequent time, detecting the service is skipped, which enables a high-speed access to the service.

While the Collector role is enabled, the service exposed by only one Sensor is accessible. To connect to more than one Sensor at the same time and access the services exposed by each Sensor, repeat enable/disable of the Collector role in order to switch access to them. At that time, perform normal connection by using the connection handle (which was obtained when connecting to each Sensor) and the handle information (which was saved when starting access to the service for the first time) as parameters.

Parameters:

<i>conhdl</i>	Connection handle	
<i>con_type</i>	RBLE_PRF_CON_DISCOVERY	Configuration connection performed when connecting for the first time
	RBLE_PRF_CON_NORMAL	Normal connection performed when connecting for the second and subsequent times
<i>*gls</i>	<i>shdl</i>	Glucose service start handle
	<i>ehdl</i>	Glucose service end handle
	<i>glucose_meas_char_hdl</i>	Glucose measurement characteristic handle
	<i>glucose_meas_val_hdl</i>	Glucose measurement characteristic value handle
	<i>glucose_meas_cfg_hdl</i>	Glucose measurement client characteristic configuration descriptor handle
	<i>glucose_meas_prop</i>	Glucose measurement characteristic property
	<i>glucose_meas_context_char_hdl</i>	Glucose measurement context characteristic handle
	<i>glucose_meas_context_val_hdl</i>	Glucose measurement context characteristic value handle
	<i>glucose_meas_context_cfg_hdl</i>	Glucose measurement context client characteristic configuration descriptor handle
	<i>glucose_meas_context_prop</i>	Glucose measurement context characteristic property
	<i>glucose_feature_char_hdl</i>	Glucose feature characteristic handle
	<i>glucose_feature_val_hdl</i>	Glucose feature characteristic value handle
	<i>glucose_feature_prop</i>	Glucose feature characteristic property
	<i>ra_cp_char_hdl</i>	RA control point characteristic handle
	<i>ra_cp_val_hdl</i>	RA control point characteristic value handle
	<i>ra_cp_cfg_hdl</i>	RA control point client characteristic configuration descriptor handle
	<i>ra_cp_prop</i>	RA control point characteristic property
<i>*dis</i>	<i>shdl</i>	Device information service start handle
	<i>ehdl</i>	Device information service end handle
	<i>sys_id_char_hdl</i>	System ID characteristic handle
	<i>sys_id_val_hdl</i>	System ID characteristic value handle
	<i>sys_id_prop</i>	System ID characteristic property

	<i>model_nb_char_hdl</i>	Model number characteristic handle
	<i>model_nb_val_hdl</i>	Model number characteristic value handle
	<i>model_nb_prop</i>	Model number characteristic property
	<i>serial_nb_char_hdl</i>	Serial number characteristic handle
	<i>serial_nb_val_hdl</i>	Serial number characteristic value handle
	<i>serial_nb_prop</i>	Serial number characteristic property
	<i>fw_rev_char_hdl</i>	Firmware revision characteristic handle
	<i>fw_rev_val_hdl</i>	Firmware revision characteristic value handle
	<i>fw_rev_prop</i>	Firmware revision characteristic property
	<i>hw_rev_char_hdl</i>	Hardware revision characteristic handle
	<i>hw_rev_val_hdl</i>	Hardware revision characteristic value handle
	<i>hw_rev_prop</i>	Hardware revision characteristic property
	<i>sw_rev_char_hdl</i>	Software revision characteristic handle
	<i>sw_rev_val_hdl</i>	Software revision characteristic value handle
	<i>sw_rev_prop</i>	Software revision characteristic property
	<i>manuf_name_char_hdl</i>	Manufacturer name characteristic handle
	<i>manuf_name_val_hdl</i>	Manufacturer name characteristic value handle
	<i>manuf_name_prop</i>	Manufacturer name characteristic property
	<i>ieee_certif_char_hdl</i>	IEEE certification characteristic handle
	<i>ieee_certif_val_hdl</i>	IEEE certification characteristic value handle
	<i>ieee_certif_prop</i>	IEEE certification characteristic property
	<i>call_back</i>	Callback
Return:		
	<i>RBLE_OK</i>	Success
	<i>RBLE_ERR</i>	Error occurred in initialization processing
	<i>RBLE_PARAM_ERR</i>	Invalid parameter
	<i>RBLE_STATUS_ERROR</i>	Not executable because the rBLE mode is other than RBLE_MODE_ACTIVE.

3.2.7 RBLE_GLP_Collector_Disable

RBLE_STATUS RBLE_GLP_Collector_Disable(uint16_t conhdl)		
This function disables the GLP Collector role and terminates the access to the service exposed by GLP Sensor. The result is reported by using the Collector role disable completion event RBLE_GLP_EVENT_COLLECTOR_DISABLE_COMP.		
Parameters:		
	<i>conhdl</i>	Connection handle
Return:		
	<i>RBLE_OK</i>	Success
	<i>RBLE_STATUS_ERROR</i>	Not executable because the rBLE mode is other than RBLE_MODE_ACTIVE.

3.2.8 RBLE_GLP_Collector_Read_Char

RBLE_STATUS RBLE_GLP_Collector_Read_Char (uint16_t conhdl, uint8_t char_code)

This function reads the characteristic value of the glucose service and the device information service.

The result is reported by using the characteristic value read request response event

RBLE_GLP_EVENT_COLLECTOR_READ_CHAR_RESPONSE.

Parameters:

<i>conhdl</i>	Connection handle	
<i>char_code</i>	RBLE_GLPC_RD_MEASUREME NT_CFG	Measurement s notification
	RBLE_GLPC_RD_MEASUREME NT_CONTEXT_CFG	Measurement s context notification
	RBLE_GLPC_RD_RA_CP_CFG	RA control point indication
	RBLE_GLPC_RD_FEATURE	Glucose feature
	RBLE_GLPC_RD_DIS_MANUF	Sensor manufacturer name
	RBLE_GLPC_RD_DIS_MODEL	Sensor model number
	RBLE_GLPC_RD_DIS_SERNB	Sensor serial number
	RBLE_GLPC_RD_DIS_HWREV	Sensor hardware revision
	RBLE_GLPC_RD_DIS_FWREV	Sensor firmware revision
	RBLE_GLPC_RD_DIS_SWREV	Sensor software revision
	RBLE_GLPC_RD_DIS_SYSID	Sensor system ID
	RBLE_GLPC_RD_DIS_IEEE	Sensor IEEE certification information

Return:

<i>RBLE_OK</i>	Success
<i>RBLE_STATUS_ERROR</i>	Not executable because the rBLE mode is other than RBLE_MODE_ACTIVE.

3.2.9 RBLE_GLP_Collector_Write_Char

RBLE_STATUS RBLE_GLP_Collector_Write_Char(uint16_t conhdl, uint8_t char_code, uint16_t cfg_val)

This function writes each client characteristic configuration descriptor of the glucose service.

The result is reported by using the characteristic value write request response event

RBLE_GLP_EVENT_COLLECTOR_WRITE_CHAR_RESPONSE.

Parameters:

<i>conhdl</i>	Connection handle	
<i>char_code</i>	RBLE_GLPC_WR_MEASUREMENT_CODE	Glucose measurement client characteristic configuration descriptor
	RBLE_GLPC_WR_MEASUREMENT_CONTEXT_CODE	Glucose measurement context client characteristic configuration descriptor
	RBLE_GLPC_WR_RA_CONTROL_POINT_CODE	RA control point client characteristic configuration descriptor
<i>cfg_val</i>	RBLE_PRF_STOP_NOTIFICATION	Stop notification or indication.
	RBLE_PRF_START_NOTIFICATION	Start notification.
	RBLE_PRF_START_INDICATION	Start indication.

Return:

<i>RBLE_OK</i>	Success
<i>RBLE_STATUS_ERROR</i>	Not executable because the rBLE mode is other than RBLE_MODE_ACTIVE.

3.2.10 RBLE_GLP_Collector_Write_RA_Control_Point

```
RBLE_STATUS RBLE_GLP_Collector_Write_RA_Control_Point(uint16_t conhdl,
    RBLE_GLP_RA_CONTROL_POINT_INFO *ra_cp_info)
```

This function sets the RA control point characteristic value of the glucose service.
Specify the request operations the OpCode.

The racp_operator is specified as follows.

If the OpCode is RBLE_GLP_OPCODE_REPORT_RECORDS, RBLE_GLP_OPCODE_DELETE_RECORDS or RBLE_GLP_OPCODE_REPORT_RECORDS_NUMBER, It can be specified RBLE_GLP_OPERATOR_LAST_RECORD, RBLE_GLP_OPERATOR_LESS, RBLE_GLP_OPERATOR_GREATER, RBLE_GLP_OPERATOR_WITHIN_RANGE, RBLE_GLP_OPERATOR_FIRST_RECORD or RBLE_GLP_OPERATOR_ALL_RECORDS.

If the OpCode is RBLE_GLP_OPCODE_ABORT_OPERATION, set RBLE_GLP_OPERATOR_NULL.

The operand_value, min_sequence_num, max_sequence_num, min_stamp and max_stamp are specified as follows.

If the racp_operator is RBLE_GLP_OPERATOR_ALL_RECORDS, RBLE_GLP_OPERATOR_FIRST_RECORD or RBLE_GLP_OPERATOR_LAST_RECORD, the operand_value, min_sequence_num, max_sequence_num, min_stamp and max_stamp are not used.

If the racp_operator is RBLE_GLP_OPERATOR_LESS and the operand_value is 0x01, specify the maximum sequence number of records to retrieve to the max_sequence_num.

If the racp_operator is RBLE_GLP_OPERATOR_LESS and the operand_value is 0x02, specify the maximum time stamp of records to retrieve to the max_stamp.

If the racp_operator is RBLE_GLP_OPERATOR_GREATER and the operand_value is 0x01, specify the minimum sequence number of records to retrieve to the min_sequence_num.

If the racp_operator is RBLE_GLP_OPERATOR_GREATER and the operand_value is 0x02, specify the minimum time stamp of records to retrieve to the min_stamp.

If the racp_operator is RBLE_GLP_OPERATOR_WITHIN_RANGE and the operand_value is 0x01, specify the maximum sequence number of records to retrieve to the max_sequence_num, and specify the minimum sequence number of records to retrieve to the min_sequence_num.

If the racp_operator is RBLE_GLP_OPERATOR_WITHIN_RANGE and the operand_value is 0x02, specify the maximum time stamp of records to retrieve to the max_stamp, and specify the minimum time stamp of records to retrieve to the min_stamp.

The result is reported by using the characteristic value write request response event RBLE_GLP_EVENT_COLLECTOR_WRITE_CHAR_RESPONSE.

Parameters:

<i>conhdl</i>	Connection handle		
<i>*ra_cp_info</i>	<i>RA control point setting value</i>		
	<i>OpCode</i>	RBLE_GLP_OPCODE_REPORT_RECORDS	Report stored records
		RBLE_GLP_OPCODE_DELETE_RECORDS	Delete stored records
		RBLE_GLP_OPCODE_ABORT_OPERATION	Abort operation
		RBLE_GLP_OPCODE_REPORT_RECORDS_NUMBER	Report number of stored records
	<i>racp_operator</i>	Operator	
		RBLE_GLP_OPERATOR_NULL	Null

RBLE_STATUS RBLE_GLP_Collector_Write_RA_Control_Point(uint16_t conhdl, RBLE_GLP_RA_CONTROL_POINT_INFO *ra_cp_info)					
			RBLE_GLP_OPERATOR _ALL_RECORDS	All records	
			RBLE_GLP_OPERATOR _LESS	Less than or equal to	
			RBLE_GLP_OPERATOR _GREATER	Greater than or equal to	
			RBLE_GLP_OPERATOR _WITHIN_RANGE	Within range of (inclusive)	
			RBLE_GLP_OPERATOR _FIRST_RECORD	First record(i.e. oldest record)	
			RBLE_GLP_OPERATOR _LAST_RECORD	Last record (i.e. most recent record)	
		<i>operand_value</i>	Operand value		
		<i>min_sequence_n um</i>	Minimum sequence number to specify a range of records		
		<i>max_sequence_n um</i>	Maximum sequence number to specify a range of records		
		<i>min_stamp</i>	Minimum time stamp to specify a range of records		
			<i>year</i>	Year	
			<i>month</i>	Month	
			<i>day</i>	Day	
			<i>hour</i>	Hour	
			<i>min</i>	Minute	
			<i>sec</i>	Second	
		<i>max_stamp</i>	Minimum time stamp to specify a range of records		
			<i>year</i>	Year	
			<i>month</i>	Month	
			<i>day</i>	Day	
			<i>hour</i>	Hour	
			<i>min</i>	Minute	
			<i>sec</i>	Second	
Return:					
<i>RBLE_OK</i>			Success		
<i>RBLE_STATUS_ERROR</i>			Not executable because the rBLE mode is other than RBLE_MODE_ACTIVE.		

3.3 Events

The following table shows the events defined for the GLP of rBLE and the following sections describe the events in detail.

Table 3-2 Events Defined for the GLP

RBLE_GLP_EVENT_SENSOR_ENABLE_COMP	Sensor role enable completion event
RBLE_GLP_EVENT_SENSOR_DISABLE_COMP	Sensor role disable completion event
RBLE_GLP_EVENT_SENSOR_ERROR_IND	Sensor role error indication event
RBLE_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_COMP	Glucose measurements send completion event
RBLE_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_CONTEXT_COMP	Glucose measurement context send completion event
RBLE_GLP_EVENT_SENSOR_SEND_RA_CP_COMP	RA control point send completion event
RBLE_GLP_EVENT_SENSOR_CHG_RA_CP_IND	RA control point change indication event
RBLE_GLP_EVENT_SENSOR_CFG_INDNTF_IND	Characteristic value indication event
RBLE_GLP_EVENT_SENSOR_COMMAND_DISALLOWED_IND	Sensor role command disallowed indication event
RBLE_GLP_EVENT_COLLECTOR_ENABLE_COMP	Collector role enable completion event
RBLE_GLP_EVENT_COLLECTOR_DISABLE_COMP	Collector role disable completion event
RBLE_GLP_EVENT_COLLECTOR_ERROR_IND	Collector role error indication event
RBLE_GLP_EVENT_COLLECTOR_MEASUREMENTS_NTF	Glucose measurement notification event
RBLE_GLP_EVENT_COLLECTOR_MEASUREMENTS_CONTEXT_NTF	Glucose measurement context notification event
RBLE_GLP_EVENT_COLLECTOR_RA_CP_IND	RA control point indication event
RBLE_GLP_EVENT_COLLECTOR_READ_CHAR_RESPONSE	Characteristic value read request response event
RBLE_GLP_EVENT_COLLECTOR_WRITE_CHAR_RESPONSE	Characteristic value write request response event
RBLE_GLP_EVENT_COLLECTOR_COMMAND_DISALLOWED_IND	Collector role command disallowed indication event

3.3.1 RBLE_GLP_EVENT_SENSOR_ENABLE_COMP

RBLE_GLP_EVENT_SENSOR_ENABLE_COMP	
This event reports the result of enabling the Sensor role (RBLE_GLP_Sensor_Enable).	
Parameters:	
<i>status</i>	Result of enabling the Sensor role (See 2.2 and <i>Bluetooth Low Energy Protocol Stack API Reference Manual: Basics, 3.2, Declaration of enumerated type for rBLE status.</i>)
<i>conhdl</i>	Connection handle

3.3.2 RBLE_GLP_EVENT_SENSOR_DISABLE_COMP

RBLE_GLP_EVENT_SENSOR_DISABLE_COMP				
This event reports the result of disabling the Sensor role (RBLE_GLP_Sensor_Disable).				
Parameters:				
<i>conhdl</i>	Connection handle			
<i>sensor_info</i>	<i>glp_meas_ntf_en</i>	RBLE_PRF_STOP_NTFFIND	Stop notification of measurement information.	
		RBLE_PRF_START_NTF	Start notification of measurement information.	
	<i>glp_meas_context_ntf_en</i>	RBLE_PRF_STOP_NTFFIND	Stop notification of measurement context information.	
		RBLE_PRF_START_NTF	Start notification of measurement context information.	
	<i>ra_cp_ind_en</i>	RBLE_PRF_STOP_NTFFIND	Stop indication of RA control point.	
		RBLE_PRF_START_IND	Start indication of RA control point.	

3.3.3 RBLE_GLP_EVENT_SENSOR_ERROR_IND

RBLE_GLP_EVENT_SENSOR_ERROR_IND	
This event indicates an error code unique to the Sensor role.	
Parameters:	
<i>conhdl</i>	Connection handle
<i>status</i>	Error code (See 2.2 and <i>Bluetooth Low Energy Protocol Stack API Reference Manual: Basics, 3.2, Declaration of enumerated type for rBLE status.</i>)

3.3.4 RBLE_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_COMP

RBLE_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_COMP	
This event reports completion of sending the measured value (RBLE_GLP_Sensor_Send_Measurements).	
Parameters:	
<i>conhdl</i>	Connection handle
<i>status</i>	Measured value send completion result (See 2.2 and <i>Bluetooth Low Energy Protocol Stack API Reference Manual: Basics, 3.2, Declaration of enumerated type for rBLE status.</i>)

3.3.5 RBLE_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_CONTEXT_COMP

RBLE_GLP_EVENT_SENSOR_SEND_MEASUREMENTS_CONTEXT_COMP	
This event reports completion of sending the measurement context information (RBLE_GLP_Sensor_Send_Measurements_Context).	
Parameters:	
<i>conhdl</i>	Connection handle
<i>status</i>	Measured value send completion result (See 2.2 and <i>Bluetooth Low Energy Protocol Stack API Reference Manual: Basics, 3.2, Declaration of enumerated type for rBLE status.</i>)

3.3.6 RBLE_GLP_EVENT_SENSOR_SEND_RA_CP_COMP

RBLE_GLP_EVENT_SENSOR_SEND_RA_CP_COMP	
This event reports completion of sending the RA control point (RBLE_GLP_Sensor_Send_RA_Control_Point).	
Parameters:	
<i>conhdl</i>	Connection handle
<i>status</i>	Measured value send completion result (See 2.2 and <i>Bluetooth Low Energy Protocol Stack API Reference Manual: Basics, 3.2, Declaration of enumerated type for rBLE status.</i>)

3.3.7 RBLE_GLP_EVENT_SENSOR_CHG_RA_CP_IND

RBLE_GLP_EVENT_SENSOR_CHG_RA_CP_IND

This event indicates that the value of the RA control point characteristic of the glucose service has been changed by the Collector.

After executing an operation code that is written to the operation of the RA control point from the Collector, respond by calling RBLE_GLP_Sensor_Send_RA_Control_Point.

If the OpCode is RBLE_GLP_OPCODE_REPORT_RECORDS, call the RBLE_GLP_Sensor_Send_RA_Control_Point after sending the record to the Collector by calling RBLE_GLP_Sensor_Send_Measurements and RBLE_GLP_Sensor_Send_Measurements_Context.

If the OpCode is RBLE_GLP_OPCODE_DELETE_RECORDS, call the RBLE_GLP_Sensor_Send_RA_Control_Point after deleting records.

If the OpCode is RBLE_GLP_OPCODE_ABORT_OPERATION, call the RBLE_GLP_Sensor_Send_RA_Control_Point after aborting the operation being performed.

If the OpCode is RBLE_GLP_OPCODE_REPORT_RECORDS_NUMBER, respond a number of records by calling the RBLE_GLP_Sensor_Send_RA_Control_Point.

Parameters:

<i>conhdl</i>	Connection handle		
	<i>OpCode</i>	RBLE_GLP_OPCODE_REPORT_RECORDS	Report stored records
		RBLE_GLP_OPCODE_DELETE_RECORDS	Delete stored records
		RBLE_GLP_OPCODE_ABORT_OPERATION	Abort operation
		RBLE_GLP_OPCODE_REPORT_RECORDS_NUMBER	Report number of stored records
	<i>racp_operator</i>	Operator	
		RBLE_GLP_OPERATOR_NULL	Null
		RBLE_GLP_OPERATOR_ALL_RECORDS	All records
		RBLE_GLP_OPERATOR_LESS	Less than or equal to
		RBLE_GLP_OPERATOR_GREATER	Greater than or equal to
		RBLE_GLP_OPERATOR_WITHIN_RANGE	Within range of (inclusive)
		RBLE_GLP_OPERATOR_FIRST_RECORD	First record(i.e. oldest record)
		RBLE_GLP_OPERATOR_LAST_RECORD	Last record (i.e. most recent record)
	<i>operand_value</i>	Operand value	
	<i>min_sequence_number</i>	Minimum sequence number to specify a range of records	
	<i>max_sequence_number</i>	Maximum sequence number to specify a range of records	
	<i>min_stamp</i>	Minimum time stamp to specify a range of records	
		<i>year</i>	Year
		<i>month</i>	Month
		<i>day</i>	Day

RBLE_GLP_EVENT_SENSOR_CHG_RA_CP_IND				
			<i>hour</i>	Hour
			<i>min</i>	Minute
			<i>sec</i>	Second
	<i>max_stamp</i>		Minimum time stamp to specify a range of records	
			<i>year</i>	Year
			<i>month</i>	Month
			<i>day</i>	Day
			<i>hour</i>	Hour
			<i>min</i>	Minute
			<i>sec</i>	Second

3.3.8 RBLE_GLP_EVENT_SENSOR_CFG_INDNTF_IND

RBLE_GLP_EVENT_SENSOR_CFG_INDNTF_IND			
This event indicates that the value of the client characteristic configuration descriptor of the glucose service has been set by the Collector.			
Parameters:			
	<i>conhdl</i>	Connection handle	
	<i>char_code</i>	RBLE_GLPC_WR_MEASUREMENT_CODE	Glucose measurement characteristic
		RBLE_GLPC_WR_MEASUREMENT_CONTEXT_CODE	Glucose measurement context characteristic
		RBLE_GLPC_WR_RA_CONTROL_POINT_CODE	RA control point characteristic
	<i>cfg_val</i>	RBLE_PRF_STOP_NTFFIND	Stop notification or indication.
		RBLE_PRF_START_NTF	Start notification.
		RBLE_PRF_START_IND	Start indication.

3.3.9 RBLE_GLP_EVENT_SENSOR_COMMAND_DISALLOWED_IND

RBLE_GLP_EVENT_SENSOR_COMMAND_DISALLOWED_IND			
This event indicates the error that occurs when a command executed by the Sensor role cannot be accepted.			
Parameters:			
	<i>status</i>	Result of command execution (See 2.2 and <i>Bluetooth Low Energy Protocol Stack API Reference Manual: Basics, 3.2, Declaration of enumerated type for rBLE status.</i>)	
	<i>opcode</i>	RBLE_CMD_GLP_SENSOR_ENABLE	Sensor role enable command
		RBLE_CMD_GLP_SENSOR_DISABLE	Sensor role disable command
		RBLE_CMD_GLP_SENSOR_SEND_MEASUREMENTS	Glucose measurement send command
		RBLE_CMD_GLP_SENSOR_SEND_MEASUREMENTS_CONTEXT	Glucose measurement context send command
		RBLE_CMD_GLP_SENSOR_SEND_RA_CONTROL_POINT	RA control point send command

3.3.10 RBLE_GLP_EVENT_COLLECTOR_ENABLE_COMP

RBLE_GLP_EVENT_COLLECTOR_ENABLE_COMP

This event reports the result of enabling the Collector role (RBLE_GLP_Collector_Enable).

Save the obtained handle information about the discovered service, to enable a high-speed access to the service without service detection when restarting access to the service.

Parameters:

<i>status</i>	Result of enabling the Collector role (See 2.2 and <i>Bluetooth Low Energy Protocol Stack API Reference Manual: Basics, 3.2, Declaration of enumerated type for rBLE status.</i>)	
	Connection handle	
<i>gls</i>	<i>shdl</i>	Glucose service start handle
	<i>ehdl</i>	Glucose service end handle
	<i>glucose_meas_char_hdl</i>	Glucose measurement characteristic handle
	<i>glucose_meas_val_hdl</i>	Glucose measurement characteristic value handle
	<i>glucose_meas_cfg_hdl</i>	Glucose measurement client characteristic configuration descriptor handle
	<i>glucose_meas_prop</i>	Glucose measurement characteristic property
	<i>glucose_meas_context_char_hdl</i>	Glucose measurement context characteristic handle
	<i>glucose_meas_context_val_hdl</i>	Glucose measurement context characteristic value handle
	<i>glucose_meas_context_cfg_hdl</i>	Glucose measurement context client characteristic configuration descriptor handle
	<i>glucose_meas_context_prop</i>	Glucose measurement context characteristic property
	<i>glucose_feature_char_hdl</i>	Glucose feature characteristic handle
	<i>glucose_feature_val_hdl</i>	Glucose feature characteristic value handle
	<i>glucose_feature_prop</i>	Glucose feature characteristic property
	<i>ra_cp_char_hdl</i>	RA control point characteristic handle
	<i>ra_cp_val_hdl</i>	RA control point characteristic value handle
	<i>ra_cp_cfg_hdl</i>	RA control point client characteristic configuration descriptor handle
	<i>ra_cp_prop</i>	RA control point characteristic property
<i>dis</i>	<i>shdl</i>	Device information service start handle
	<i>ehdl</i>	Device information service end handle
	<i>sys_id_char_hdl</i>	System ID characteristic handle
	<i>sys_id_val_hdl</i>	System ID characteristic value handle
	<i>sys_id_prop</i>	System ID characteristic property
	<i>model_nb_char_hdl</i>	Model number characteristic handle
	<i>model_nb_val_hdl</i>	Model number characteristic value handle
	<i>model_nb_prop</i>	Model number characteristic property
	<i>serial_nb_char_hdl</i>	Serial number characteristic handle
	<i>serial_nb_val_hdl</i>	Serial number characteristic value handle
	<i>serial_nb_prop</i>	Serial number characteristic property
	<i>fw_rev_char_hdl</i>	Firmware revision characteristic handle
	<i>fw_rev_val_hdl</i>	Firmware revision characteristic value handle
	<i>fw_rev_prop</i>	Firmware revision characteristic property

	<i>hw_rev_char_hdl</i>	Hardware revision characteristic handle
	<i>hw_rev_val_hdl</i>	Hardware revision characteristic value handle
	<i>hw_rev_prop</i>	Hardware revision characteristic property
	<i>sw_rev_char_hdl</i>	Software revision characteristic handle
	<i>sw_rev_val_hdl</i>	Software revision characteristic value handle
	<i>sw_rev_prop</i>	Software revision characteristic property
	<i>manuf_name_char_hdl</i>	Manufacturer name characteristic handle
	<i>manuf_name_val_hdl</i>	Manufacturer name characteristic value handle
	<i>manuf_name_prop</i>	Manufacturer name characteristic property
	<i>ieee_certif_char_hdl</i>	IEEE certification characteristic handle
	<i>ieee_certif_val_hdl</i>	IEEE certification characteristic value handle
	<i>ieee_certif_prop</i>	IEEE certification characteristic property

3.3.11 RBLE_GLP_EVENT_COLLECTOR_DISABLE_COMP

RBLE_GLP_EVENT_COLLECTOR_DISABLE_COMP		
This event reports the result of disabling the Collector role (RBLE_GLP_Collector_Disable).		
Parameters:		
<i>status</i>	Result of disabling the Collector role (See 2.2 and <i>Bluetooth Low Energy Protocol Stack API Reference Manual: Basics, 3.2, Declaration of enumerated type for rBLE status.</i>)	
<i>conhdl</i>	Connection handle	

3.3.12 RBLE_GLP_EVENT_COLLECTOR_ERROR_IND

RBLE_GLP_EVENT_COLLECTOR_ERROR_IND		
This event indicates an error code unique to the GLP Collector role.		
Parameters:		
<i>status</i>	Error code (See 2.2 and <i>Bluetooth Low Energy Protocol Stack API Reference Manual: Basics, 3.2, Declaration of enumerated type for rBLE status.</i>)	
<i>conhdl</i>	Connection handle	

3.3.13 RBLE_GLP_EVENT_COLLECTOR_MEASUREMENTS_NTF

RBLE_GLP_EVENT_COLLECTOR_MEASUREMENTS_NTF

This event indicates the measured value sent from the Sensor.

Parameters:

<i>conhdl</i>	Connection handle		
	<i>flags</i>	<i>seq_num</i>	Flag that defines whether there is a data field in the characteristic value or not
			Sequence number
	<i>stamp</i>	Time stamp	
		<i>year</i>	Year
		<i>month</i>	Month
		<i>day</i>	Day
		<i>hour</i>	Hour
		<i>min</i>	Minute
		<i>sec</i>	Second
	<i>time_offset</i>		Time offset
	<i>concentration</i>		Glucose Concentration (kg/L or mol/L)
	<i>type</i>	Type	
		RBLE_GLP_TYPE_CAPIL LARY_WHOLE_BLOOD	Capillary Whole blood
		RBLE_GLP_TYPE_CAPIL LARY_PLASMA	Capillary Plasma
		RBLE_GLP_TYPE_VENO US_WHOLE_BLOOD	Venous Whole blood
		RBLE_GLP_TYPE_VENO US_PLASMA	Venous Plasma
		RBLE_GLP_TYPE_ARTE RIAL_WHOLE_BLOOD	Arterial Whole blood
		RBLE_GLP_TYPE_ARTE RIAL_PLASMA	Arterial Plasma
		RBLE_GLP_TYPE_UNDE TERMINED_WHOLE_BLO OD	Undetermined Whole blood
		RBLE_GLP_TYPE_UNDE TERMINED_PLASMA	Undetermined Plasma
		RBLE_GLP_TYPE_ISF	Interstitial Fluid (ISF)
		RBLE_GLP_TYPE_CONT ROL_SOLUTION	Control Solution
	<i>sample_location</i>	Sample location	
		RBLE_GLP_SAMPLELO C_FINGER	Finger
		RBLE_GLP_SAMPLELO C_AST	Alternate Site Test (AST)
		RBLE_GLP_SAMPLELO C_EARLOBE	Earlobe

RBLE_GLP_EVENT_COLLECTOR_MEASUREMENTS_NTF				
		<i>sensor_status_annun</i>	RBLE_GLP_SAMPLELOC_CONTROL_SOLUTION	Control solution
			RBLE_GLP_SAMPLELOC_NOT_AVAILABLE	Sample Location value not available
			Sensor status annunciation	
			RBLE_GLP_SENSORSTATUS_DEVICE_BATTERY_LOW	Device battery low at time of measurement
			RBLE_GLP_SENSORSTATUS_MALFUNCTION_FAULTING	Sensor malfunction or faulting at time of measurement
			RBLE_GLP_SENSORSTATUS_INSUFFICIENT	Sample size for blood or control solution insufficient at time of measurement
			RBLE_GLP_SENSORSTATUS_STRIP_INSERTION_ERROR	Strip insertion error
			RBLE_GLP_SENSORSTATUS_STRIP_TYPE_INCORRECT	Strip type incorrect for device
			RBLE_GLP_SENSORSTATUS_RESULT_HIGH	Sensor result higher than the device can process
			RBLE_GLP_SENSORSTATUS_RESULT_LOW	Sensor result lower than the device can process
			RBLE_GLP_SENSORSTATUS_TEMPERATURE_HIGH	Sensor temperature too high for valid test/result at time of measurement
			RBLE_GLP_SENSORSTATUS_TEMPERATURE_LOW	Sensor temperature too low for valid test/result at time of measurement
			RBLE_GLP_SENSORSTATUS_READ_INTERRUPTED	Sensor read interrupted because strip was pulled too soon at time of measurement
			RBLE_GLP_SENSORSTATUS_GENERAL_DEVICE_FAULT	General device fault has occurred in the sensor
			RBLE_GLP_SENSORSTATUS_TIME_FAULT	Time fault has occurred in the sensor and time may be inaccurate

3.3.14 RBLE_GLP_EVENT_COLLECTOR_MEASUREMENTS_CONTEXT_NTF

RBLE_GLP_EVENT_COLLECTOR_MEASUREMENTS_CONTEXT_NTF

This event indicates the measurement context value sent from the Sensor.

Parameters:

<i>conhdl</i>	Connection handle		
<i>measure_context_info</i>	<i>flags</i>	Flag that defines whether there is a data field in the characteristic value or not	
	<i>seq_num</i>	Sequence number	
	<i>ex_flags</i>	Extended flags	
	<i>carbohydrate_id</i>	Carbohydrate ID	
		RBLE_GLP_CARBOHYD RATEID_BREAKFAST	Breakfast
		RBLE_GLP_CARBOHYD RATEID_LUNCH	Lunch
		RBLE_GLP_CARBOHYD RATEID_DINNER	Dinner
		RBLE_GLP_CARBOHYD RATEID_SNACK	Snack
		RBLE_GLP_CARBOHYD RATEID_DRINK	Drink
		RBLE_GLP_CARBOHYD RATEID_SUPPER	Supper
		RBLE_GLP_CARBOHYD RATEID_BRUNCH	Brunch
	<i>carbohydrate_kg</i>	Carbohydrate – units of kilograms	
	<i>meal</i>	Meal	
		RBLE_GLP_MEAL_PREP RANDIAL	Preprandial (before meal)
		RBLE_GLP_MEAL_POST PRANDIAL	Postprandial (after meal)
		RBLE_GLP_MEAL_FAST ING	Fasting
		RBLE_GLP_MEAL_CASU AL	Casual (snacks, drinks, etc.)
		RBLE_GLP_MEAL_BEDT IME	Bedtime
	<i>tester</i>	Tester	
		RBLE_GLP_TESTER_SE LF	Self
		RBLE_GLP_TESTER_HE ALTH_CARE_PRO	Health Care Professional
		RBLE_GLP_TESTER_LA B_TEST	Lab test
		RBLE_GLP_TESTER_N OT_AVAILABLE	Tester value not available
	<i>health</i>	Health	

RBLE_GLP_EVENT_COLLECTOR_MEASUREMENTS_CONTEXT_NTF				
			RBLE_GLP_HEALTH_MINOR_ISSUE	Minor health issues
			RBLE_GLP_HEALTH_MAJOR_ISSUE	Major health issues
			RBLE_GLP_HEALTH_DURING_MENSES	During menses
			RBLE_GLP_HEALTH_UNDER_STRESS	Under stress
			RBLE_GLP_HEALTH_NO_ISSUE	No health issues
			RBLE_GLP_HEALTH_NOT_AVAILABLE	Health value not available
		<i>exercise_duration</i>	Exercise Duration	
		<i>exercise_intensity</i>	Exercise Intensity	
		<i>medication_id</i>	Medication ID	
			RBLE_GLP_MEDICATION_ID_RAPID_INSULIN	Rapid acting insulin
			RBLE_GLP_MEDICATION_ID_SHORT_INSULIN	Short acting insulin
			RBLE_GLP_MEDICATION_ID_INTERMEDIATE_INSULIN	Intermediate acting insulin
			RBLE_GLP_MEDICATION_ID_LONG_INSULIN	Long acting insulin
			RBLE_GLP_MEDICATION_ID_PREMIXED_INSULIN	Pre-mixed insulin
		<i>medication</i>	Medication (kg or litter)	
		<i>HbA1c</i>	HbA1c	

3.3.15 RBLE_GLP_EVENT_COLLECTOR_RA_CP_IND

RBLE_GLP_EVENT_COLLECTOR_RA_CP_IND

This event indicates the response of RA control point operation sent from the Sensor.
 Check that the value of the request_op_code is the same as the operation code sent by the RA control point setting API (RBLE_GLP_Collector_Write_RA_Control_Point).
 If the OpCode is RBLE_GLP_OPCODE_NUMBER_RECORDS_RESPONSE, retrieve the number of records from num_of_records.
 If the OpCode is RBLE_GLP_OPCODE_RESPONSE_CODE, confirm the execution result of operation in response_code_value.

Parameters:

<i>conhdl</i>	Connection handle		
<i>ra_cp_info</i>	<i>OpCode</i>	RBLE_GLP_OPCODE_NUMBER_RECORDS_RESPONSE	Number of stored records response
		RBLE_GLP_OPCODE_RESPONSE_CODE	Response Code
	<i>racp_operator</i>	RBLE_GLP_OPERATOR_NULL	Null
	<i>num_of_records</i>	Number of records	
	<i>request_op_code</i>	RBLE_GLP_OPCODE_REPORT_RECORDS	Report stored records
		RBLE_GLP_OPCODE_DELETE_RECORDS	Delete stored records
		RBLE_GLP_OPCODE_ABORT_OPERATION	Abort operation
		RBLE_GLP_OPCODE_REPORT_RECORDS_NUMBER	Report number of stored records
	<i>response_code_value</i>	RBLE_GLP_OPERAND_SUCCESS	Success
		RBLE_GLP_OPERAND_OPCODE_NOT_SUPPORTED	Op Code not supported
		RBLE_GLP_OPERAND_INVALID_OPERATOR	Invalid Operator
		RBLE_GLP_OPERAND_OPERATOR_NOT_SUPPORTED	Operator not supported
		RBLE_GLP_OPERAND_INVALID_OPERAND	Invalid Operand
		RBLE_GLP_OPERAND_NO_RECORD	No records found
		RBLE_GLP_OPERAND_ABORT_UNSUCCESSFUL	Abort unsuccessful
		RBLE_GLP_OPERAND_NOT_COMPLETED	Procedure not completed
		RBLE_GLP_OPERAND_NOT_SUPPORTED	Operand not supported

3.3.16 RBLE_GLP_EVENT_COLLECTOR_READ_CHAR_RESPONSE

RBLE_GLP_EVENT_COLLECTOR_READ_CHAR_RESPONSE			
This event reports the response to the characteristic value read request (RBLE_GLP_Collector_Read_Char). Read out the read data in accordance with the contents of the request.			
Parameters:			
<i>conhdl</i>	Connection handle		
<i>att_code</i>	0x00	Characteristic value successfully acquired	
	Other than 0x00	Error occurred when acquiring characteristic value	
<i>data</i>	<i>each_len</i>	Length of each result	
	<i>len</i>	Data length	
	<i>data[RBLE_ATT_M_MAX_VALUE]</i>	Read characteristic data	

3.3.17 RBLE_GLP_EVENT_COLLECTOR_WRITE_CHAR_RESPONSE

RBLE_GLP_EVENT_COLLECTOR_WRITE_CHAR_RESPONSE			
This event reports the response to the characteristic value write request (RBLE_GLP_Collector_Write_Char).			
Parameters:			
<i>conhdl</i>	Connection handle		
<i>att_code</i>	0x00	Characteristic value successfully written	
	Other than 0x00	Error occurred when writing characteristic value	

3.3.18 RBLE_GLP_EVENT_COLLECTOR_COMMAND_DISALLOWED_IND

RBLE_GLP_EVENT_COLLECTOR_COMMAND_DISALLOWED_IND			
This event indicates the error that occurs when a command executed by the Collector role cannot be accepted.			
Parameters:			
<i>status</i>	Result of command execution (See 2.2 and <i>Bluetooth Low Energy Protocol Stack API Reference Manual: Basics, 3.2, Declaration of enumerated type for rBLE status.</i>)		
<i>opcode</i>	RBLE_CMD_GLP_COLLECTOR_ENABLE		Collector role enable command
	RBLE_CMD_GLP_COLLECTOR_DISABLE		Collector role disable command
	RBLE_CMD_GLP_COLLECTOR_READ_CHAR		Characteristic read command
	RBLE_CMD_GLP_COLLECTOR_WRITE_CHAR		Characteristic write command
	RBLE_CMD_GLP_COLLECTOR_WRITE_RA_CONT ROL_POINT		RA control point setup command

3.4 Message Sequence Chart

T.B.D.

4. Notes

Appendix A How to Read Definition Tables

This section shows how to read the tables that describes the rBLE API functions and events shown in this document.

A.1 How to Read Function Definition Tables

The following contents are included in the function definition tables:

The Parameters area describes the parameters specified for the function. The italicized character strings on the left are the parameters of the function. The meaning of each parameter is described on the far right following the variables.

The italicized character string(s) next to each parameter indicate the member(s) of the parameter (structure).

The values that can be specified for the parameter might be described between the parameter name and its description.

The function definition is shown at the top of the table in the row with the light green background. This area shows the function prototype.

The operation of the function and the event reported after executing the function are described in this area.

Parameters:			
<i>Parameter 1</i>	Description of parameter 1		
<i>Parameter 2</i>	<i>Member 1</i>	Value 1 that can be specified for member 1	Description of value 1 that can be specified for member 1
		Value 1 that can be specified for member 2	Description of value 1 that can be specified for member 2
	<i>Member 2</i>	Description of member 2	
Return:			
<i>Value 1 that might be returned</i>		Description of value 1 that might be returned	
<i>Value 2 that might be returned</i>		Description of value 2 that might be returned	

The Return area describes the values returned for the function. The leftmost row shows the value that might be returned, and the next row describes the return value.

A.2 How to Read Event Definition Tables

The following contents are included in the event definition tables:

The Parameters area describes the parameters specified for the event. The italicized character strings on the left show the parameters of the event parameter structure. The meaning of each parameter is described on the far right.

The italicized character string(s) next to each parameter indicate the member(s) of the parameter (structure).

The event definition is shown at the top of the table in the row with the orange background. This area shows the event type.

The information reported by the event is described in this area.

Parameters:

<i>Parameter 1</i>	Description of parameter 1	
<i>Parameter 2</i>	<i>Member 1</i>	Description of member 1
	<i>Member 2</i>	Description of member 2
	<i>Member 3</i>	Description of member 3
<i>Parameter 3</i>	Value 1 that can be specified for parameter 3	Description of value 1 that can be specified for parameter 3
	Value 2 that can be specified for parameter 3	Description of value 2 that can be specified for parameter 3

The values that can be specified for the parameter might be shown between the parameter name and its description.

Appendix B Referenced Documents

1. Bluetooth Core Specification v4.0, Bluetooth SIG
2. Find Me Profile Specification v1.0, Bluetooth SIG
3. Immediate Alert Service Specification v1.0, Bluetooth SIG
4. Proximity Profile Specification v1.0, Bluetooth SIG
5. Link Loss Service Specification v1.0, Bluetooth SIG
6. Tx Power Service Specification v1.0, Bluetooth SIG
7. Health Thermometer Profile Specification v1.0, Bluetooth SIG
8. Health Thermometer Service Specification v1.0, Bluetooth SIG
9. Device Information Service Specification v1.1, Bluetooth SIG
10. Blood Pressure Profile Specification v1.0, Bluetooth SIG
11. Blood Pressure Service Specification v1.0, Bluetooth SIG
12. HID over GATT Profile Specification v1.0, Bluetooth SIG
13. HID Service Specification v1.0, Bluetooth SIG
14. Battery Service Specification v1.0, Bluetooth SIG
15. Scan Parameters Profile Specification v1.0, Bluetooth SIG
16. Scan Parameters Service Specification v1.0, Bluetooth SIG
17. Heart Rate Profile Specification v1.0, Bluetooth SIG
18. Heart Rate Service Specification v1.0, Bluetooth SIG
19. Cycling Speed and Cadence Profile Specification v1.0, Bluetooth SIG
20. Cycling Speed and Cadence Service Specification v1.0, Bluetooth SIG
21. Cycling Power Profile Specification v0.9, Bluetooth SIG
22. Cycling Power Service Specification v0.9, Bluetooth SIG
23. Glucose Profile Specification v1.0, Bluetooth SIG
24. Glucose Service Specification v1.0, Bluetooth SIG
25. Bluetooth SIG Assigned Numbers <https://www.bluetooth.org/Technical/AssignedNumbers/home.htm>
26. Services & Characteristics UUID <http://developer.bluetooth.org/gatt/Pages/default.aspx>
27. Personal Health Devices Transcoding White Paper v1.2, Bluetooth SIG

Appendix C Terminology

Term	Description
Service	A service is provided from a GATT server to a GATT client. The GATT server exposes some characteristics as the interface. The service prescribes how to access the exposed characteristics.
Profile	A profile enables implementation of a use case by using one or more services. The services used are defined in the specifications of each profile.
Characteristic	A characteristic is a value used to identify services. The characteristics to be exposed and their formats are defined by each service.
Role	Each device takes the role prescribed by the profile or service in order to implement the specified use case.
Client Characteristic Configuration Descriptor	A descriptor is used to control notifications or indications of characteristic values that include the client characteristic configuration descriptor sent from the GATT server.
Server Characteristic Configuration Descriptor	A descriptor is used to control broadcast of characteristic values that include the server characteristic configuration descriptor sent from the GATT server.
Connection Handle	The handle determined by the controller stack and is used to identify connection with a remote device. The valid handle range is between 0x0000 and 0x0EFF.

REVISION HISTORY	Bluetooth Low Energy Protocol Stack API Reference Manual: GLP
------------------	---

Rev.	Date	Description	
		Page	Summary
0.12	Jan 30, 2015	---	Provisional Edition issued
1.00	Apr 17, 2015	2	The service definitions are updated.

Bluetooth Low Energy Protocol Stack
API Reference Manual: GLP

Publication Date: Rev.1.00 Apr 17, 2015

Published by: Renesas Electronics Corporation



SALES OFFICES

Renesas Electronics Corporation

<http://www.renesas.com>

Refer to "<http://www.renesas.com/>" for the latest and detailed information.

Renesas Electronics America Inc.

2801 Scott Boulevard Santa Clara, CA 95050-2549, U.S.A.
Tel: +1-408-588-6000, Fax: +1-408-588-6130

Renesas Electronics Canada Limited

9251 Yonge Street, Suite 8309 Richmond Hill, Ontario Canada L4C 9T3
Tel: +1-905-237-2004

Renesas Electronics Europe Limited

Dukes Meadow, Millboard Road, Bourne End, Buckinghamshire, SL8 5FH, U.K.
Tel: +44-1628-585-100, Fax: +44-1628-585-900

Renesas Electronics Europe GmbH

Arcadiastrasse 10, 40472 Düsseldorf, Germany
Tel: +49-211-6503-0, Fax: +49-211-6503-1327

Renesas Electronics (China) Co., Ltd.

Room 1709, Quantum Plaza, No.27 ZhiChunLu Haidian District, Beijing 100191, P.R.China
Tel: +86-10-8235-1155, Fax: +86-10-8235-7679

Renesas Electronics (Shanghai) Co., Ltd.

Unit 301, Tower A, Central Towers, 555 Langao Road, Putuo District, Shanghai, P. R. China 200333
Tel: +86-21-2226-0888, Fax: +86-21-2226-0999

Renesas Electronics Hong Kong Limited

Unit 1601-1611, 16/F., Tower 2, Grand Century Place, 193 Prince Edward Road West, Mongkok, Kowloon, Hong Kong
Tel: +852-2265-6688, Fax: +852 2886-9022

Renesas Electronics Taiwan Co., Ltd.

13F, No. 363, Fu Shing North Road, Taipei 10543, Taiwan
Tel: +886-2-8175-9600, Fax: +886 2-8175-9670

Renesas Electronics Singapore Pte. Ltd.

80 Bendemeer Road, Unit #06-02 Hyflux Innovation Centre, Singapore 339949
Tel: +65-6213-0200, Fax: +65-6213-0300

Renesas Electronics Malaysia Sdn.Bhd.

Unit 1207, Block B, Menara Amcorp, Amcorp Trade Centre, No. 18, Jln Persiaran Barat, 46050 Petaling Jaya, Selangor Darul Ehsan, Malaysia
Tel: +60-3-7955-9390, Fax: +60-3-7955-9510

Renesas Electronics India Pvt. Ltd.

No.777C, 100 Feet Road, HALII Stage, Indiranagar, Bangalore, India
Tel: +91-80-67208700, Fax: +91-80-67208777

Renesas Electronics Korea Co., Ltd.

12F., 234 Teheran-ro, Gangnam-Gu, Seoul, 135-080, Korea
Tel: +82-2-558-3737, Fax: +82-2-558-5141

Bluetooth Low Energy Protocol Stack



Renesas Electronics Corporation

R01UW0103EJ0100